

ArcGIS for Desktop Cookbook

Over 60 hands-on recipes to help you become a more productive ArcGIS Desktop user

Daniela Cristiana Docan



ArcGIS for Desktop Cookbook

Over 60 hands-on recipes to help you become a more productive ArcGIS for Desktop user

Daniela Cristiana Docan



ArcGIS for Desktop Cookbook

Copyright © 2015 Packt Publishing

All rights reserved. No part of this book may be reproduced, stored in a retrieval system, or transmitted in any form or by any means, without the prior written permission of the publisher, except in the case of brief quotations embedded in critical articles or reviews.

Every effort has been made in the preparation of this book to ensure the accuracy of the information presented. However, the information contained in this book is sold without warranty, either express or implied. Neither the author, nor Packt Publishing, and its dealers and distributors will be held liable for any damages caused or alleged to be caused directly or indirectly by this book.

Packt Publishing has endeavored to provide trademark information about all of the companies and products mentioned in this book by the appropriate use of capitals. However, Packt Publishing cannot guarantee the accuracy of this information.

First published: January 2015

Production reference: 1170115

Published by Packt Publishing Ltd. Livery Place 35 Livery Street Birmingham B3 2PB, UK.

ISBN 978-1-78355-950-3

www.packtpub.com

Cover image by Daniela Cristiana Docan (daniela.docan@utcb.ro)

Credits

Author

Daniela Cristiana Docan

Project Coordinator Danuta Jones

Reviewers

Ken Doman Stefano Iacovella Tram Vu Khanh Truong John (Yiguang) Zhang

Commissioning Editor Pramila Balan

Acquisition Editor Llewellyn Rozario

Content Development Editor Mohammed Fahad

Technical Editors Humera Shaikh Mohita Vyas

Copy Editor Sarang Chari

Proofreaders

Simran Bhogal Sandra Hopper Joanna McMahon

Indexer Mariammal Chettiyar

Production Coordinator Alwin Roy

Cover Work Alwin Roy

About the Author

Daniela Cristiana Docan is currently a lecturer in the Department of Topography and Cadastre at the Faculty of Geodesy in Bucharest, Romania. She obtained her PhD in 2009 from Technical University of Civil Engineering Bucharest with the thesis *Contributions to quality improvement of spatial data in GIS*. Formerly, she worked for Esri Romania and the National Agency of Cadastre and Land Registration (ANCPI).

While working for Esri Romania, she trained teams (as an authorized instructor in ArcGIS Desktop by Environmental Systems Research Institute, Inc., USA) from state and privately owned companies, such as Romanian Civil Aeronautical Authority, Agency of Payments and Intervention for Agriculture (APIA), Institute of Hydroelectric Studies and Design, and Petrom. She has also trained and assisted the team in charge of quality data control using ArcGIS for Desktop and PLTS GIS Data ReViewer in the Land Parcels Identification System (LPIS) project, in Romania.

For the ANCPI, in 2009, she created the conceptual, logical, and physical data model for the Romanian National Topographic Dataset at the scale 1:5,000 (TOPR05). She was a member of the workgroup that elaborated TOPR05 and metadata technical specifications for the ANCPI and the Member State Report for Infrastructure for Spatial Information in the European Community (INSPIRE) in 2010.

I would like to thank Llewellyn Rozario, Mohammed Fahad, Humera Shaikh, Mohita Vyas, and everyone else from Packt Publishing for all their hard work to get this book published.

I would also like to thank the reviewers for their work and practical advice.

A special thanks goes to my friends for their support.

About the Reviewers

Ken Doman is a GIS developer for Bruce Harris & Associates, Inc., a land-record mapping and software development company that is an Esri Business Partner. Ken has worked both in municipal government GIS and in the private sector. He has experienced many facets of GIS technology, from field data collection and GPS to mapping and data analysis to publishing web maps and applications.

Ken previously reviewed *Building Web and Mobile ArcGIS Server Applications with JavaScript, Eric Pimpler Packt Publishing.* He is also in the middle of writing another book for Packt Publishing on a similar topic.

I would first like to thank my wife, who puts up with my night-owl tendencies when working on these books. I would also like to thank Bruce Harris & Associates, Inc., for giving me opportunities and exposure to learn more about GIS technologies. I would also like to thank the City of Plantation, Florida, and the City of Jacksonville, Texas, for providing career opportunities for me in GIS. Thanks also goes out to Packt Publishing, who found me out of the blue and let me read cool stuff such as this book. Finally, I would like to thank God, without whom I believe none of this would be possible. **Stefano lacovella** is a longtime GIS developer and consultant living in Rome, Italy. He also routinely works as a GIS course instructor.

He obtained a PhD in Geology. Having a very curious mind, he developed a deep knowledge of IT technologies, mainly focusing on GIS software and related standards.

Starting his career as an Esri employee, he was exposed to and became confident with proprietary GIS software, mainly the Esri suite of products.

In the last 14 years, he has become more and more involved with open source software, also integrating it with proprietary software. He loves the open source approach and really trusts collaboration and sharing of knowledge. He strongly believes in the open source idea and constantly manages to spread it out in all sectors, not just the GIS sector.

He has been using GeoServer since release 1.5, configuring, deploying, and hacking it in several projects. Other GFOSS projects he mainly uses and likes are GDAL/OGR, PostGIS, QGIS, and OpenLayers.

He authored two books on GeoServer with Packt Publishing: GeoServer Cookbook, a practical set of recipes to get the most out of the software, and GeoServer Beginner's Guide, a first approach to GeoServer features.

When not playing with maps and geometric shapes, he loves reading about science, mainly physics and math ematics; riding his bike; and having fun with his wife and his two daughters, Alice and Luisa.

You can contact him at stefano.iacovella@gmail.com or follow him on Twitter at @iacovellas.

Tram Vu Khanh Truong received her Master's degree in Regional and City Planning from the University of Oklahoma. Currently, she is a transportation planner at the Greensboro Urban Area Metropolitan Planning Organization in Greensboro, North Carolina. Her duties include GIS development, data analysis, and transportation system planning. Tram Truong has a passion for utilizing GIS in transportation planning to support decision making and linking multimodal transportation planning with mixed-use land development planning. **John (Yiguang) Zhang** has been in the geospatial industry for over 20 years with a strong background in GIS, software development, database management, photogrammetry, and remote sensing. He has been working as a software developer and GIS analyst for the past 15 years and has experienced various GIS projects from start to finish on GIS application design, development, and implementation as well as GIS analysis and map production. He has also managed complex spatial databases and experienced a lot of spatial data conversion and integration processes. His creative thinking skills have helped him solve problems effectively through the course of his career in the public and private sectors, such as City of Chilliwack and Intergraph Corporation. He is proficient with the Esri ArcGIS family of products, including ArcGIS Desktop and ArcGIS Server, and spatial database management systems, such as Oracle Spatial, SQL Server, and open source PostgreSQL/PostGIS. He is also competent in .NET and Web 2.0 technologies. He holds a master's degree in Digital Photogrammetry and an Advanced Diploma in GIS from British Columbia Institute of Technologies, Canada.

Firstly, I'd like to thank to my wife, Winnie, for dedicating her time in taking care of the family and for her patience with this wonderful book review and other projects. I would also like to thank my son, Sylvester, and daughter, Sylvia, for their bright ideas to the problems I had to solve.

www.PacktPub.com

Support files, eBooks, discount offers, and more

For support files and downloads related to your book, please visit www.PacktPub.com.

Did you know that Packt offers eBook versions of every book published, with PDF and ePub files available? You can upgrade to the eBook version at www.PacktPub.com and as a print book customer, you are entitled to a discount on the eBook copy. Get in touch with us at service@packtpub.com for more details.

At www.PacktPub.com, you can also read a collection of free technical articles, sign up for a range of free newsletters and receive exclusive discounts and offers on Packt books and eBooks.



https://www2.packtpub.com/books/subscription/packtlib

Do you need instant solutions to your IT questions? PacktLib is Packt's online digital book library. Here, you can search, access, and read Packt's entire library of books.

Why subscribe?

- ► Fully searchable across every book published by Packt
- Copy and paste, print, and bookmark content
- On demand and accessible via a web browser

Free access for Packt account holders

If you have an account with Packt at www.PacktPub.com, you can use this to access PacktLib today and view 9 entirely free books. Simply use your login credentials for immediate access.

Table of Contents

Preface	1
Chapter 1: Designing Geodatabase	7
Introduction	7
Creating a file geodatabase	8
Creating a feature dataset	10
Creating a feature class	12
Creating subtypes	15
Creating domains	19
Using subtypes and domains together	23
Creating a relationship class	28
Chapter 2: Editing Data	37
Introduction	37
Editing features in a geodatabase	37
Advanced editing in a geodatabase	48
Creating geodatabase topology	55
Editing geodatabase topology	62
Chapter 3: Working with CRS	71
Introduction	71
Understanding projections	74
Projecting vector data	79
Georeferencing raster data	88
Setting a custom coordinate reference system	93
Chapter 4: Geoprocessing	99
Introduction	99
Spatial joining features	100
Using spatial adjustment	106

Table of Contents	
Using common tools	111
Creating models	116
Chapter 5: Working with Symbology	125
Introduction	125
Managing styles	126
Modifying symbols	131
Creating custom symbology	135
Using proportional symbology	139
Using the symbol levels	142
Using representation	145
Chapter 6: Building Better Maps	153
Introduction	153
Creating and editing labels	154
Labeling with Maplex Label Engine	159
Creating and editing annotation	164
Using annotation and masking for contours	173
Creating a bivariate map	176
Chapter 7: Exporting Your Maps	181
Introduction	181
Creating a map layout	182
Exporting your map to the PDF and GeoTIFF formats	197
Creating an atlas of maps	199
Publishing maps on the Internet	204
Chapter 8: Working with Geocoding and Linear Referencing	209
Introduction	209
Preparing data for geocoding	210
Geocoding addresses	214
Geocoding with alternative names	222
Creating and editing routes	228
Creating and editing events	233
Working with complex routes	237
Analyzing events	240
Chapter 9: Working with Spatial Analyst	245
Introduction	245
Analyzing surfaces	246
Interpolating data	255
Reclassifying a raster	260
Working with Map Algebra	265
Working with Cell Statistics	271

—**ii**—

	——— Table of Contents
Generalizing a raster	276
Creating density surfaces	279
Analyzing the least-cost path	283
Chapter 10: Working with 3D Analyst	291
Introduction	291
Creating 3D features from 2D features	292
Creating a TIN surface	297
Creating a terrain dataset	300
Creating raster and TIN from a terrain dataset	306
Intervisibility	309
Creating a profile graph	311
Creating an animation	315
Chapter 11: Working with Data Interoperability	321
Introduction	321
Exporting file geodatabase to different data formats	322
Importing data from the XML format	328
Importing vector data	332
Importing raster data	336
Spatial ETL	340
Index	351

Preface

ArcGIS for Desktop is an important component of the Esri ArcGIS platform. ArcGIS for Desktop allows you to visualize, create, analyze, manage, and distribute geographic data.

ArcGIS for Desktop Cookbook starts with the basics of designing a file geodatabase schema. Using your file geodatabase schema, you will learn to create, edit, and constrain the geometry and attribute values of your data. In this book, you will learn to manage Coordinate Reference System (CRS) issues in the geodatabase context.

This book will also cover the following topics: designing and sharing quality maps, geocoding addresses, creating routes and events, analyzing and visualizing raster data in 3D environments, and exporting/importing different data formats.

Knowing and understanding your data is essential in any spatial analysis and geoprocessing process. Therefore, you will work with two main geodatabase structures that fully support all topics covered by this book's chapters.

ArcGIS for Desktop Cookbook will clearly explain all the basic steps performed in every recipe of the book to help you refine your own workflow.

What this book covers

Chapter 1, *Designing Geodatabase*, teaches you how to create a file geodatabase for a topographic map. It shows you, step by step, how to create feature datasets, feature classes, subtypes, and domains. Furthermore, you will create relationship classes and test the relationship behavior.

Chapter 2, Editing Data, teaches you how to add data to your file geodatabase created in *Chapter 1, Designing Geodatabase.* In addition to this, you will learn to work with COordinate GeOmetry (COGO) elements, such as bearings, angles, and horizontal distances. You will identify all invalid attribute values for the newly created or loaded features in accordance with the domains created in the first chapter. You will also constrain and administrate the spatial relationships between features with geodatabase topology.

Preface -

Chapter 3, Working with CRS, explains how to transform a CRS into another CRS using a predefined ArcGIS Project tool. You will also learn how to georeference a scanned topographic map. Furthermore, you will learn to define a custom CRS and a custom transformation.

Chapter 4, Geoprocessing, guides you through the geoprocessing tools for vector data, such as Spatial Join, Spatial Adjustment, Attribute transfer, Buffer, and Intersect. In addition to this, you will learn to work with the Model Builder application. You will build a geoprocessing workflow for a project named VeloGIS. This small project will analyze the possible consequences of creating a cycling infrastructure, taking into account the existing road network.

Chapter 5, Working with Symbology, teaches you how to manage a collection of symbols, colors, and map elements into a style format. The chapter also covers the *Representation* topic that refers to an advanced technique to symbolize geographic features on a map.

Chapter 6, Building Better Maps, teaches you how to create labels with Maplex Label Engine. The chapter also covers the *Annotation* topic, which refers to an advanced technique to label the geographic features. In addition to this, you will learn to create a quantitative bivariate map, which analyzes two variables from census data: level of education and unemployment rate for a country/region.

Chapter 7, Exporting Your Maps, teaches you how to design, prepare, and export quality maps. Finally, you will publish your maps on ArcGIS Online.

Chapter 8, Working with Geocoding and Linear Referencing, teaches you how to convert the address information into spatial data and how to manage and use these geocoded addresses. The second part of this chapter will show you how to build routes and events for three different bus lines and a complex route for delivering a customer service.

Chapter 9, Working with Spatial Analyst, teaches you how to work with and analyze raster data. It shows you, step by step, how to create a terrain surface, reclassify a raster, work with Map Algebra and statistical functions, generalize a raster, generate density surfaces, and perform a least-cost path analysis.

Chapter 10, Working with 3D Analyst, teaches you how to create 3D features from 2D features and how to create TIN and Terrain surfaces. You will analyze the visibility between buildings and three geodetic points from the ground, using the ArcScene application. Moreover, you will create an animated fly-by tour of your 3D buildings and Digital Terrain Model (DTM) in ArcScene and will export it to a video file.

Chapter 11, Working with Data Interoperability, teaches you how to manage different data formats. You will export and import a file geodatabase using the XML interchange format. The second part of this chapter will show you how to import vector data into your geodatabase using the ArcGIS Data Interoperability extension.

2

What you need for this book

To complete the exercises in this book, you will need to have installed ArcGIS 10.x for Desktop (Advanced) and the ArcGIS Data Interoperability for Desktop extension.

Depending on your software version, please download and install the latest patches (bug fixes) or service packs (compilation of bug fixes) from http://support.esri.com/en/downloads/patches-servicepacks.

You need to have access to an Internet connection to publish your map in the Publishing maps on the Internet recipe of Chapter 7, Exporting Your Maps.

Data used in this book is freely available on the Packt Publishing site.

Who this book is for

ArcGIS for Desktop Cookbook is written for GIS users who already have basic knowledge about ArcGIS, but need to increase their productivity using the ArcGIS for Desktop applications and extensions. Even if you don't have previous experience with ArcGIS, this book is useful for you because it will help you to catch up with acquainted users.

Please insert the following here:

Sections

In this book, you will find several headings that appear frequently (Getting ready, How to do it, How it works, There's more, and See also).

To give clear instructions on how to complete a recipe, we use these sections as follows:

Getting ready

This section tells you what to expect in the recipe, and describes how to set up any software or any preliminary settings required for the recipe.

How to do it...

This section contains the steps required to follow the recipe.

How it works...

This section usually consists of a detailed explanation of what happened in the previous section.



Preface

There's more...

This section consists of additional information about the recipe in order to make the reader more knowledgeable about the recipe.

See also

This section provides helpful links to other useful information for the recipe.

Conventions


In this book, you will find a number of styles of text that distinguish between different kinds of information. Here are some examples of these styles, and an explanation of their meaning.

Code words in text, database table names, folder names, filenames, file extensions, pathnames, dummy URLs, user input, and Twitter handles are shown as follows: "In the next step, you will create a file geodatabase named Topo5k.gdb for a topographic map corresponding to the scale 1:5,000."

A block of code is set as follows:

```
HYC[int] = HIC[int]
Name[string] = Name[string]
HType[int] = HAT[int]
```

New terms and important words are shown in bold. Words that you see on the screen, for example, in menus or dialog boxes, appear in the text like this: "Select ArcToolbox from the Standard toolbar. Go to Data Management Tools | Workspace, and double-click on the Create File GDB tool."





Tips and tricks appear like this.



Reader feedback

Feedback from our readers is always welcome. Let us know what you think about this book—what you liked or disliked. Reader feedback is important for us as it helps us develop titles that you really get the most out of.

To send us general feedback, simply e-mail feedback@packtpub.com, and mention the book title via the subject of your message.

If there is a topic that you have expertise in and you are interested in either writing or contributing to a book, see our author guide at www.packtpub.com/authors.

Customer support

Now that you are the proud owner of a Packt book, we have a number of things to help you to get the most from your purchase.

Downloading the example code

You can download the example code files from your account at http://www.packtpub.com for all the Packt Publishing books you have purchased. If you purchased this book elsewhere, you can visit http://www.packtpub.com/support and register to have the files e-mailed directly to you.

Downloading the color images of this book

We also provide you with a PDF file that has color images of the screenshots/diagrams used in this book. The color images will help you better understand the changes in the output. You can download this file from: https://www.packtpub.com/sites/default/files/ downloads/B00189 95030T Graphics.pdf.

Errata

Although we have taken every care to ensure the accuracy of our content, mistakes do happen. If you find a mistake in one of our books—maybe a mistake in the text or the code—we would be grateful if you would report this to us. By doing so, you can save other readers from frustration and help us improve subsequent versions of this book. If you find any errata, please report them by visiting http://www.packtpub.com/submit-errata, selecting your book, clicking on the **Errata Submission Form** link, and entering the details of your errata. Once your errata are verified, your submission will be accepted and the errata will be uploaded on our website, or added to any list of existing errata, under the Errata section of that title.

5

Preface -

To view the previously submitted errata, go to https://www.packtpub.com/books/ content/support and enter the name of the book in the search field. The required information will appear under the **Errata** section.

Piracy

Piracy of copyrighted material on the Internet is an ongoing problem across all media. At Packt, we take the protection of our copyright and licenses very seriously. If you come across any illegal copies of our works in any form on the Internet, please provide us with the location address or website name immediately so that we can pursue a remedy.

Please contact us at copyright@packtpub.com with a link to the suspected pirated material.

We appreciate your help in protecting our authors and our ability to bring you valuable content.

Questions

If you have a problem with any aspect of this book, you can contact us at questions@packtpub.com, and we will do our best to address the problem.



1 Designing Geodatabase

In this chapter, we will cover the following recipes:

- Creating a file geodatabase
- Creating a feature dataset
- Creating a feature class
- Creating subtypes
- Creating domains
- Using subtypes and domains together
- Creating a relationship class

Introduction

Real-world objects can be represented in **Geographic Information Systems (GIS)** using geographic data. In the context of the **Esri ArcGIS** technology, a database that stores geographic data is a geodatabase. The geodatabase is a native **ArcGIS** format that allows you to store, edit, and manage spatial data and non-spatial data. Before you start adding data to a geodatabase, it is important to think about how your data will be organized in the geodatabase. Another important step is to create an empty but structured schema of your geodatabase (data model). Paul A. Longley (Geographical Information Systems and Science, 2nd Edition, 2005, John Wiley & Sons, Inc , p.178) has mentioned three steps in creating a geospatial data model:

- 1. Conceptual schema
- 2. Logical schema
- 3. Physical schema (geodatabase schema)

Designing Geodatabase

In this chapter, you will skip steps 1 and 2, and you will manually create the physical schema or the geodatabase structure.

- Carlor

There are three types of geodatabases: personal geodatabase, file geodatabase, and multiuser geodatabase. For more information about geodatabases, please refer to http://www.esri.com/software/arcgis/geodatabase.

For comprehensive definitions of specific elements and terms such as geodatabase, file geodatabase, feature dataset, spatial domain, resolution, tolerance, subtype, domain, feature class, relationship, or referential integrity, please refer to the ESRI GIS Dictionary online at http://support.esri.com/en/knowledgebase/GISDictionary.

In this chapter, you will work with the most common geodatabase elements, such as feature dataset, feature class, table, and relationship class. You will test the main advantages of using a geodatabase by performing the following actions:

- Define the common spatial reference using feature datasets
- Organize the features with the same geometry and spatial reference in feature classes
- Define attribute constraints to eliminate edit errors using subtypes, domains, and default values
- > Define spatial and non-spatial relationships using relationship classes
- Add supplementary spatial and attribute behaviors by defining relationship rules for relationship classes

Creating a file geodatabase

In this chapter, all exercises will refer to the single-user file geodatabase format. A file geodatabase is suited to ArcGIS for Desktop users and is stored in a filesystem folder. The main advantages of a file geodatabase are:

- > Editing of different feature classes or tables at the same time by multiple users
- A maximum size of up to 1 terabyte (TB) for the individual datasets stored in a file geodatabase



If you decide to use a single-user geodatabase for your project, but you are still thinking about the two options, personal geodatabase and file geodatabase, then please read the paper *The Top Nine Reasons to Use a File Geodatabase*: http://www.esri.com/news/arcuser/0309/files/9reasons.pdf.



Getting ready

In the next step, you will create a file geodatabase named Topo5k.gdb for a topographic map corresponding to the scale 1:5,000.

How to do it...

Follow these steps to create a new file geodatabase in ArcCatalog using the context menu:

- 1. Start ArcCatalog. Select **Connect To Folder** from the **Standard** toolbar. Go to <drive>:\PacktPublishing\Data, and click on **OK**.
- 2. In **Catalog Tree**, select <drive>:\PacktPublishing\Data, and right-click to choose **New | Folder**. Rename **New Folder** as MyGeodatabase.
- 3. In Catalog Tree, select MyGeodatabase, and right-click to choose New | New File Geodatabase. Rename New File Geodatabase.gdb as Topo5k.

Downloading the example code

You can download the example code files for all Packt books you have purchased from your account at http://www.packtpub.com. If you purchased this book elsewhere, you can visit http://www. packtpub.com/support and register to have the files e-mailed directly to you.

How it works...

You have created an empty file geodatabase using the context menu in ArcCatalog. You will use **Topo5k.gdb** in the later steps. Open Windows Explorer to see the structure of the filesystem folder created for your file geodatabase.

There's more...

Follow these steps to create a new file geodatabase in ArcCatalog using ArcToolbox:

- 1. Select ArcToolbox from the Standard toolbar. Go to Data Management Tools | Workspace, and double-click on the Create File GDB tool.
- For File GDB Location, select Folder Connections, go to <drive>:\
 PacktPublishing\Data, and select the MyGeodatabase folder. For File GDB
 Name, type Topo5000. For File GDB Version (optional), select the CURRENT option
 to create a file geodatabase compatible with ArcGIS Version 10.2, and click on OK.



Designing Geodatabase

See also

- ► For more information about creating a file geodatabase, please refer to Chapter 11, Working with Data Interoperability
- In the next recipe, Creating a feature dataset, you will learn how to organize your spatial datasets using feature datasets in a file geodatabase

Creating a feature dataset

A feature dataset is a container for feature classes that have the same spatial reference, **Coordinate Reference System** (**CRS**), spatial domain, resolution, and tolerance. In the case of importing features with the same CRS, the feature dataset will accept only the features that have their coordinates between the minimum and maximum values defined for the *x*, *y*, *z* and *m* values of spatial domain extent. A feature dataset cannot contain other feature datasets or non-spatial tables.



For more details about the feature dataset, please refer to the *online ArcGIS help* (10.2) by navigating to **Geodata** | **Data types** | **Feature datasets** from http://resources.arcgis.com/en/help/main/10.2.

Getting ready

You will create seven feature datasets: Buildings, GeodeticPoints, Hydrography, LandUse, Relief, Transportation, and Boundaries. In your file geodatabase, Topo5k. gdb, all feature datasets will have the same CRS.


How to do it...

Follow these steps to create feature datasets in a file geodatabase using the ArcCatalog context menu:

- Start ArcCatalog. In Catalog Tree, go to <drive>:\PacktPublishing\Data\ MyGeodatabase, and select Topo5k.gdb.
- Right-click on Topo5k.gdb, and navigate to New | Feature Dataset for the Name type Buildings. Click on Next. Navigate to Projected Coordinate Systems | National Grids | Europe | Pulkovo 1942 Adj 1958 Stereo 1970. Select the active yellow star Add To Favorites to add the selected projected coordinate system to the Favorites section. You will use this projected coordinate system later in this book.
- 3. Click on Next. Navigate to Vertical Coordinate Systems | Europe | Constanta. Click on Next. Accept the XY, Z, and M tolerance values. Keep checked the option Accept default resolution and domain extent (recommended).



- 4. If you want to see the default values for resolution and domain extent, uncheck them and click on **Next**. Examine the default values, and click on the **Finish** button.
- 5. If you want to examine the default values for domain, resolution, and tolerance, right-click on Buildings feature datasets and navigate to the **Properties** | **Domain**, **Resolution** and **Tolerance** tabs.
- 6. Repeat the previous steps to create the following feature datasets: GeodeticPoints, Hydrography, LandUse, Relief, and Transportation, as shown in the following screenshot:



7. To inspect the results, return to the Feature Dataset Properties dialog.

How it works...

After you have created a feature dataset, ArcCatalog allows you to change only the XY and Z coordinate system. If you take the decision to change the XY coordinate system for a feature dataset, you should know that you cannot modify the values for domain, resolution and tolerance. If you still need to change the CRS for a feature dataset, it will be more proper to create the feature dataset from the beginning. In conclusion, when you are thinking about a feature dataset, think twice and act once.

There's more...

In ArcCatalog, you can use **Copy** and **Paste** from the context menu in the file geodatabase to duplicate the first feature dataset. In the **Data Transfer** window, you can change the name of the feature dataset by typing in the **Target Name** section. In this case, the newly resulted feature dataset will have the same coordinate reference system as the source feature dataset.

See also

▶ For more information about CRS, please refer to Chapter 3, Working with CRS

11

Designing Geodatabase

Creating a feature class

Features are representations of the real-word objects in a geodatabase. Features are grouped in classes based on their common components: shape (geometry) and attributes. Features from a feature class share the same spatial reference. A feature class stores simple features (for example, point, multipoint, line, and polygon) or non-simple features (for example, dimension and annotation). When a feature class is created, the user can add two optional geometry properties for features: *z* value (3D data) and *m* value (used for linear referencing). The feature class table contains some default attribute fields, which are managed by ArcGIS: **OBJECTID** and **SHAPE**. The **OBJECTID** field has the **Object ID** type property and stores the unique identifier for each feature. The **SHAPE** field refers to the **Geometry** type property and stores the *x* and *y* coordinates of the features and optionally *z* and *m* values if the feature class has the *z* and/or *m* properties enabled. The feature class that stores line or polygon features has two supplementary fields: **SHAPE_Length** (length of the feature line) and **SHAPE_Area** (area of the feature polygon).



For more details about the feature class and field data types, please refer to Geodata/Data types/Feature Class and Geodata/Geodatabases/Defining the properties of data in a geodatabase/Geodatabase table properties/ ArcGIS field data types from ArcGIS help (10.2) online.

Usually, feature classes are stored inside a feature dataset and automatically inherit the spatial reference of the feature dataset. A feature class that is stored at the root level of a geodatabase is a standalone feature class and has its own spatial reference.

Getting ready

You will continue to work at the geodatabase structure by creating four feature classes: Buildings (polygon features), Watercourse (polygon features), WatercourseL (polyline features), and LandUse (polygon features).

How to do it...

Follow these steps to create feature classes using the ArcCatalog context menu:

 Start ArcCatalog. In Catalog Tree, go to <drive>:\PacktPublishing\Data\ MyGeodatabase\Topo5k.gdb.

12

13 –

2. Right-click on the Buildings feature dataset, and choose New | Feature Class. For Name, type Buildings and for Alias, type Buildings. For Type, choose Polygon Feature. Leave the Geometry Properties options unchecked. Click on Next. Select Default for the Configuration Keyword section. Click on Next. There are two default attribute fields: OBJECTID and SHAPE. You will create five new attribute fields: BD (Alias=Destination), BM (Alias=Material), Stories (Alias=Number of stories), BS (Alias=State of buildings) and LandUseID. For Field Name, in the first empty cell below SHAPE, type BD, and for Data Type, select Long Integer from the drop-down list. In the Field Properties section, for the Alias, type Destination and for Allow NULL values, select Yes. Leave empty the Default Value property. You will add the default value later on in this chapter. You should see something similar to the following screenshot:

eature Class Properties			
General Editor Tracking Fields Indexes Sub	XY Coordinate System	Domain, Resolution a	
Indexes Sub	types Feature Extent	Relationships Rep	presentations
Field	Name	Data Type	~
OBJECTID		Object ID	
SHAPE		Geometry	
BD		Long Integer	
SHAPE_Length		Double	
SHAPE_Area		Double	
BM		Long Integer	
Stories		Long Integer	
BS		Text	
			~
Click any field to see its prope Field Properties			
Alias	Number of stories		
Allow NULL values	Yes		
Default Value			
Domain			
		Impor	t
To add a new field, type the r the Data Type column to choo			k in
	0	K Cancel	Apply

Designing Geodatabase -

- 3. Repeat step 2 for BM (Default Value: 0), Stories, and LandUseID.
- 4. For the BS attribute field, choose Text from the drop-down list. Notice that the Field Properties options have changed according to the data type. For Alias, type State of buildings, and for the Length property, type 4. Click on OK to close the Feature Class Properties dialog. To inspect the results, return to the Feature Class Properties dialog. Right-click on the Buildings feature class, and navigate to Properties | Fields. Notice the two geometry attribute fields: SHAPE_Length and SHAPE_Area.
- 5. Right-click on the Hydrography feature dataset, and navigate to New | Feature Class. For Name, type Watercourse, and for Alias, type Watercourse. For Type, choose Polygon Feature. Leave the Geometry Properties options unchecked. Click on Next. Select Default for the Configuration Keyword section. Click on Next, and add the following attribute fields:

Name	Data type	Alias	Allow NULL values	Default Value
НТуре	Long Integer	Water category	Yes	<none></none>
HYC	Long Integer	Hydrologic category	Yes	<none></none>

- 6. Click on OK to close the Feature Class Properties dialog.
- 7. Right-click on the Hydrography feature dataset, and choose New | Feature Class. For Name, type WatercourseL and for Alias, type WatercourseL. For Type, choose Line Feature. Leave the Geometry Properties options unchecked. Click on Next. Select Default for the Configuration Keyword section. Click on Next. You will add field definitions by selecting the Import button. Navigate to Topo5k.gdb | Hydrography, and select the Watercourse polygon feature class. Click on Add. You now have two attribute fields: HType (Water category), HYC (Hydrologic category), along with Name. Click on OK.
- 8. Right-click on LandUse, and choose New | Feature Class. For Name, type LandUse and for Type, choose Polygon Feature. Click on Next twice, and add the following attribute fields:

Name	Data type	Alias	Allow NULL values	Default Value
CAT	Long Integer	Category	Yes	<none></none>
SCAT	Text with Length 5	SubCategory	Yes	<none></none>

9. Click on **OK** to close the **Feature Class Properties** dialog. Return to the **Feature Class Properties** dialog for every feature class to inspect the results.



How it works...

For every feature class, you defined different attribute fields. Because the WatercourseL feature class has the same attribute fields as Watercourse, you imported the field definitions from Watercourse at step 7. For all attribute fields, you have selected **Yes** for **Allow NULL values**. When you add a new feature in **ArcMap**, the attribute field will have a NULL value or an empty value that will be ignored by the functions in ArcMap. To enforce data integrity, you can specify that a field cannot contain empty or null values by setting **Allow NULL values** to **No**. This condition can be validated in the ArcMap edit session using the **Validate Features** option from **Editor** in **Editor toolbar**. You have another option to enforce field values by setting the **Default Value** property. A default value is automatically assigned to an attribute field when a new feature is being created in the ArcMap edit session.

There's more...

Regarding spatial reference of the feature class, if you want to move WatercourseL in the LandUse feature dataset, you simply select the feature class and drag and drop it into the LandUse feature dataset. You will succeed because both feature datasets have the same spatial reference. If you drag and drop the WatercourseL feature class into the root of the geodatabase, you will have a standalone feature class.

See also

 In the following Creating subtypes recipe, you will learn how to group features in a feature class based on a subtype field

Creating subtypes

Subtypes are properties of feature classes or non-spatial tables. The subtypes gather the features from a feature class or records from a non-spatial table that share the same attribute values using an attribute field. The attribute field that groups the features must be of the data type **Short** or **Long integer**, and it will be named the subtype field. A feature class can have only one subtype field. You can assign different behaviors to individual subtypes from a feature class/table. Generally speaking, the behavior is defined by the actions or characteristics of features in a geodatabase. A subtype has a code and a description. After you have defined the subtypes for a subtype field, you can change everything related to a subtype: change the value or description of code, add more codes, and delete code. The subtypes help you in the geometry editing process and prevent errors when editing feature attribute values. The subtypes maintain the integrity in a geodatabase.

15

Designing Geodatabase

Getting ready

You will continue to work with geodatabase schema by grouping features from the feature classes that you created in the previous *Creating a feature class* recipe. The integer subtype fields are the following: BD for Buildings, HType for Watercourse and WatercourseL, and CAT for LandUse.

How to do it...

Follow these steps to define subtypes using the context menu in ArcCatalog:

- Start ArcCatalog. In Catalog Tree, go to <drive>:\PacktPublishing\Data\ MyGeodatabase\ Topo5k.gdb\Buildings.
- 2. Right-click on the Buildings feature class, and navigate to Properties | Fields. You will define five subtypes for the BD attribute field. Select the Subtypes tab in the Feature Class Properties window. For Subtype Field, select the drop-down arrow and choose BD. In the Subtypes section, you have a default subtype with Code with the value 0 and Description with the value New Subtype. Change Description of the first subtype by typing Unknown.

3.	Continue to create subtypes as shown in the following table:

Code	Description	Code	Description
0	Unknown	3	Industrial and municipal
1	Dwelling	4	Historical sites, monuments, statues
2	Administrative buildings and socialcultural	5	Dwelling annex

4. For Default Subtype, choose the Dwelling subtype. Click on Apply and on OK. Open the Feature Class Properties dialog for the Buildings feature class to check the subtypes you just added. Right-click on the Buildings feature class, and choose Properties | Subtypes. You should see something similar to the following screenshot:

- 16

Chapter 1

General E	ditor Trac		ystem Domair	n, Resolu	tion and Toleranc
Fields Inc	exes	Subtypes Feature E	xtent Relation	nships 📗	Representation
ubtype Field:		BD		*	
efault Subtyp		. III			
zerault subtyp	е.	Dwelling		*	
iubtypes:					
Code		Description		~	
0	Unknov	vn			
1	Dwellin	g			
2		strative buildings and socia	lcultural		
3		ial and municipal			
4	Historic	al sites,monuments,statue	3		
4	Historic		3		
4	Historic	al sites,monuments,statue	3	>	
4	Historic Dwellin	al sites,monuments,statue α annex	3	>	
4 5 <	Historic Dwellin and Dom	al sites,monuments,statue α annex	s Domain	>	
4 5 Cefault Values	Historic Dwellin and Dom ame	al sites,nonuments,statue α annex ains:		>	
4 5 Cefault Values Field N	Historic Dwellin and Dom ame gth	al sites,nonuments,statue α annex ains:			
4 5 Cefault Values Field N SHAPE_Leng	Historic Dwellin and Dom ame gth	al sites,nonuments,statue α annex ains:			
4 5 Sefault Values Field N SHAPE_Leng SHAPE_Ares BM Stories	Historic Dwellin and Dom ame gth	al sites,nonuments,statue α annex ains:			
4 5 Cefault Values Field N SHAPE_Leng SHAPE_Area BM	Historic Dwellin and Dom ame gth	al sites,nonuments,statue α annex ains:			
4 5 Sefault Values Field N SHAPE_Len SHAPE_Are: BM Stories BS	Historic Dwellin and Dom ame gth	al sites,nonuments,statue α annex ains:			
4 5 Sefault Values Field N SHAPE_Leng SHAPE_Ares BM Stories	Historic Dwellin and Dom ame gth	al sites,nonuments,statue α annex ains:			
4 5 Sefault Values Field N SHAPE_Len SHAPE_Are: BM Stories BS	Historic Dwellin and Dom ame gth a	al sites,nonuments,statue α annex ains:			

5. In **Catalog Tree**, select the **Hydrography** feature dataset. Right-click on the Watercourse feature class, and choose **Properties** | **Fields**. Select the **Subtypes** tab in the **Feature Class Properties** window. You will define five subtypes for the HType attribute field. For **Subtype Field** select the drop-down arrow, choose HType, and add the following subtypes:

Code	Description	Code	Description
0	Unknown	3	Creek
1	River	4	Canalized stream
2	Stream		

6. For **Default Subtype** choose the **River** subtype. Click on **Apply** and on **OK**. Open the **Feature Class Properties** dialog for the **Watercourse** feature class to check the subtypes you just added.



Designing Geodatabase -

- 7. Repeat step 4 to create subtypes for the **WatercourseL** feature class using the same codes and descriptions.
- 8. Repeat step 4 to create subtypes for the **LandUse** feature class using the **CAT** (**Description**: Category) attribute field and the following subtypes:

Code	Description	Code	Description
0	Unknown	21	Forest
11	Arable	31	Hydrography
12	Pasture	41	Transportation
13	Meadow	42	Other terrains
14	Vineyard	51	Unproductive
15	Fruit orchard		

- 9. For **Default Subtype**, choose the **Arable** subtype. Click on **Apply** and on **OK**. Open the **Feature Class Properties** dialog for the **LandUse** feature class to check the subtypes you just added.
- 10. Inspect the results in Subtypes in the Feature Class Properties dialog.

How it works...

The subtypes will help you to edit feature geometry and attribute fields faster. The default subtype is used as the default edit target for the **Watercourse** feature class when you start an edit session in ArcMap. In the **Feature Class Properties** dialog, you can add more subtypes for the **BD** attribute field, and you can delete a subtype or change **Code** and **Description**.



If you delete all code, your feature class will not have subtypes anymore, and all rules and behaviors related to subtypes will be corrupt or lost for the feature class.

Sometimes, when you are establishing codes and descriptions for a subtype field, it is impossible to anticipate correctly all possible values. It is good practice to add code that covers all unforeseen values: **Code**: 42 and **Description**: Other terrains. Another good practice is to add code that refers to the situation in which you know the values for all other attribute fields, but you are not sure about the subtype, and it will be defined later: **Code**: 0 and **Description**: Unknown.

See also

► For information about how you can enforce attribute values for a feature class table, please refer to the following *Creating domains* recipe



Creating domains

The domains define the valid values for the attribute fields of feature classes or non-spatial tables. The domains are properties of a geodatabase, and obviously are stored at the geodatabase level. In a feature class/table, an attribute field can have one or many domains associated with it. The multiple domains associated with a field are based on the existing subtypes that you have already defined for a feature class. A domain can be associated with one or many attribute fields of one or more feature classes from a geodatabase.

There are two domain types: **Range** and **Coded Values**. A range domain defines minimum and maximum values and can be used only by the numeric and date field types. A coded domain can be used by the numeric, date, and text field types and defines an explicit list of valid values. Every valid value has a code and a description. A domain defines the attribute behavior when a feature is split or merged in ArcMap using the **Split policy** and the **Merge policy**.



For more details about domains, please refer to Geodata/Data types/ Domains from ArcGIS help (10.2) online.

Getting ready

Let's continue to work with geodatabase schema by defining valid values for the attribute fields of feature classes that you created in the *Creating a feature class* recipe. You will create the domains in the geodatabase **Properties**.

In the Database Properties dialog, the Domains section has three main sections:

- > Domain Name | Description: This defines domain name and description
- Domain Properties: This sets the domain properties, such as the data type, domain type and split/merge policy
- Coded Values: This defines the codes and descriptions

How to do it...

Follow these steps to create domains using the ArcCatalog context menu:

 Start ArcCatalog. In Catalog Tree, go to <drive>:\PacktPublishing\Data\ MyGeodatabase\Topo5k.gdb. Right-click on the Topo5k.gdb file geodatabase, and select Properties | Domains.



Designing Geodatabase -

2. In the first cell from the Domain Name column, type dBM. For the Description column, type Building material. In the second section, Domain Properties, for the Field Type tab, choose Long Integer from the drop-down list. For Domain Type, select Coded Values from the drop-down list. For Split policy, select Duplicate and for Merge policy, leave Default Value. You will establish the default values later in this recipe. In the Coded Values section, add the following codes and descriptions:

Code	Description	Code	Description
0	Unknown	4	Clay
1	Concrete	5	Mixture
2	Brick	6	Metal
3	Wood	100	Other

3. To save changes, click on **Apply** from time to time. You should see something similar to the following screenshot:

Database Properties		×					
General Domains	General Domains						
Domain Name	Description	^					
dArable	Land use						
dBM	Building material						
dForest	Land use						
dFruitOrchard	Land use						
dHYC	Hydrologic category						
dHydrography	Land use						
dMeadow	Land use						
dOtherTerrain	Land use						
Domain Properties:							
Field Type	Long Integer	~					
Domain Type	Coded Values						
Split policy	Duplicate						
Merge policy	Default Value						
		_					
		_					
Coded Values:							
Code	Description	~					
	Concrete						
	Brick						
3 Wood	Wood						
4 Clav	Clav						
	OK Cancel	Apply					



- 4. Create a new domain named dStories with **Description** of Number of stories. In the **Domain Properties** section, for the **Field Type** option, choose **Long Integer**. For **Domain Type**, select **Range** from the drop-down list. For **Minimum value**, type 1, and for **Maximum value**, type 6. For **Split policy**, select **Duplicate**, and for **Merge policy**, leave **Default Value**.
- 5. Create a new domain named dState with Description: State of building. In the Domain Properties section, for the Field Type option, choose Text. For Domain Type, select Coded Values from the drop-down list. For Split policy, select Duplicate, and for Merge policy, leave Default Value. You will establish the default values later in this recipe. In the Coded Values section, add the following code and description:

Code	Description	Code	Description
fb	Very good	r	Bad condition
b	Good	i	Insanitary
s	Satisfactory	С	Construction

- 6. To save changes, click on Apply from time to time.
- 7. The next domain is dHYC. For the Description column, type Hydrologic category. In the Domain Properties section, for the Field Type option, choose Long Integer. For Domain Type, select Coded Values from the drop-down list. For Split policy, select Duplicate, and for Merge policy, leave Default Value. In the Coded Values section, add the following code and description:

С	ode	Description	Code	Description
0		Unknown	2	Intermittent
1		Perennial	3	Ephemeral

- 8. Create a last domain dUnkn. For the Description column, type Unknown Text. In the Domain Properties section, for the Field Type option, choose Text. For Domain Type, select Coded Values from the drop-down list. For Split policy, select Duplicate, and for Merge policy, leave Default Value. In the Coded Values section, you will add the code and description. For the Code column, type Unkn, and for Description, type Unknown.
- 9. Click on Apply to save changes. Click on OK to close the Database Properties window.
- 10. Right-click on **Topo5k.gdb**, and navigate to **Properties** | **Domains** to inspect the results.

21

Designing Geodatabase

How it works...

At step 2, for **Split policy**, you selected **Duplicate**. When you split a building made of Brick material (domain code: 2) during the edit session in ArcMap, you will have two buildings made from bricks. For **Merge policy**, you selected **Default Value**. Let's suppose you already established the **Default Value** option for the BM (Building material) field to 0. When you merge two buildings made of Brick material (domain code: 2) during the edit session in ArcMap, you will have two buildings made of Unknown material (domain code: 0). The range and coded values can be validated in the ArcMap edit session using the **Validate Features** option from **Editor** present in the **Editor** toolbar. The **Validate Features** option helps you to find mistaken attribute values in the sense that it is not a valid value.

There's more...

To create a new coded value domain for a file geodatabase, based on a table that contains the defined codes and descriptions for a domain, you can use the **Table To Domain** tool from **ArcToolbox**. In ... \Data\DesigningGeodatabase\LandUseDomains folder, you have five dBASE tables corresponding to the following domains: dArable, dPasture, dMeadow, dVineyard, and dFruitOrchard.

Follow these steps to create more domains for your file geodatabase using ArcToolbox:

- 1. Select **ArcToolbox** from the **Standard** toolbar. Navigate to **Data Management Tools** | **Domains**, and double-click on the **Table To Domain** tool. Set the following parameters:
 - Set the Input Table parameter as ...\Data\DesigningGeodatabase\ LandUseDomains\Arable.dbf
 - Set the Code Field option as CodeArable
 - Set the Description Field option as Descript
 - □ Set the Input Workspace field as ... \Data\MyGeodatabase\Topo5k.gdb
 - Set the **Domain Name** field as dArable
 - Set the Domain Description (optional) field as Land Use domain from table
 - Accept default option for the Update Option (optional) field
- 2. Click on OK to close the Table To Domain dialog.
- 3. Open the **Database Properties** dialog for the Topo5k.gdb feature class to check the subtypes you just added. Repeat step 1 to add the dPasture, dMeadow, dVineyard, and dFruitOrchard domains.

22

See also

 In the Using subtypes and domains together recipe, you will learn how to combine subtypes and domains for the feature classes you just created

Using subtypes and domains together

In this recipe, you will use both subtypes and domains to better control, constrain, and partially automate the editing processes of the field values.

Getting ready

In this section, you will assign default values and domains to fields and subtype fields for the following feature classes: Buildings, Watercourse, WatercourseL, and LandUse.

The exercise tests three cases:

- ► A simple domain assigned to the BM (Material), Stories (Number of stories), and BS (State of buildings) attribute fields for the Buildings feature class.
- ► Two feature classes will share the same domain. The dHYC domain will be assigned to the HYC (Hydrologic category) attribute field for the Watercourse and WatercourseL feature classes.
- Six domains will be assigned to a single attribute field based on the subtypes of the LandUse feature class. The dUnkn, dArable, dPasture, dMeadow, dVineyard, and dFruitOrchard domains will assign to the SCAT (SubCategory) attribute field for the LandUse feature class based on the subtypes defined for the CAT (Category) subtype field.

How to do it...

Follow these steps to assign domains to attribute fields of the feature classes:

- 1. Start ArcCatalog. In **Catalog Tree**, go to ...\Data\MyGeodatabase\ Topo5k. gdb\Buildings.
- Right-click on the Buildings feature class, and navigate to Properties | Fields. Select the BD attribute field. In Field Properties, the Default Value field is 1 because Default Subtype is Dwelling with code with a value of 1. To see the subtypes, select the Subtypes tab. For every subtype, you will assign three different domains to the following fields: BM, Stories, and BS.



Designing Geodatabase -

3. In the Subtypes section, select the Unknown subtype by clicking the small box on the left-hand side of the row with code the value of which is 0. The rows will become black. In the Default Values and Domains section, set the Default Value and Domain columns, as shown in the following screenshot:

De	Default Values and Domains:							
	Field Name Default Value Domain							
	SHAPE_Length							
	SHAPE Area							
	BM	0	dBM					
	Stories	1	dStories					
	BS	b	dState					

- 4. The default value 0 for the BM field corresponds to the Unknown description. The default value 1 for the Stories field corresponds to a building with one storey. The default value b for the BS field corresponds to a Good state of building. Click on **Apply** to save changes.
- 5. Select the Dwelling subtype. In the **Default Values and Domains** section, set the **Default Value** and **Domain** columns, as shown in the following screenshot:

0 1 E 0 T			
General Editor Tra			Resolution and Toleranc
Fields Indexes	Sublypes Feat	ure Extent Relations	nips Representation
<u>S</u> ubtype Field:	BD		~
Default Subtype:	D		
Deradic Subcype.	Dwelling		¥
Subtypes:			1
Code Unkno	Descri	otion	
1 Dwell			
	istrative buildings and	socialcultural	444
	rial and municipal		-
	ical sites,monuments,s	tatues	
	na annex		<u> </u>
			>
Default Values and Dor	nains:		
Field Name	Default Value	Domain	
SHAPE_Length			
SHAPE_Area			-
BM	2	dBM	
Stories	1	dStories	
BS	b	dState	
<			>
Use Defaults		Domains	



- 6. When you define values in the **Default Value** field, you must think what the most common value used for the Dwelling subtype is. For example, most of the dwellings are made of brick (domain code: 2). During an edit session, when a feature is added, split, or merged, the default value will be assigned to the attribute field value.
- 7. Continue to assign the same domains to the next four subtypes. Click on **Apply** and on **OK** to save and close the **Feature Class Properties** dialog.
- 8. In **Catalog Tree**, select the Hydrography feature dataset. Right-click on the Watercourse feature class, and navigate to **Properties** | **Fields**. Select the **HType** attribute field. In **Field Properties**, the **Default Value** field is 1 because the **Default Subtype** field is River, where **Code** is 1.
- For every subtype, you will assign a single domain to the HYC attribute field. In the Subtypes section, select the Unknown subtype, and set the Default Value and Domain columns, as shown in the following screenshot:

Default Values and Domains:						
Field Name	Default Value	Domain				
HYC	0	dHYC				
Name						
SHAPE_Length						
SHAPE_Area						

10. Continue to assign values to the **Default Values and Domain** section for the rest of the subtypes, as shown in the following table:

Subtype code	Code description	Field	Default Value	Description	Domain
1	River	HYC	1	(Perennial)	dHYC
2	Stream	HYC	2	(Intermittent)	dHYC
3	Creek	HYC	3	(Ephemeral)	dhyc
4	Canalized stream	HYC	1	(Perennial)	dHYC



Designing Geodatabase

- 11. Click on Apply and on OK to save and close the Feature Class Properties dialog.
- 12. In **Catalog Tree**, select the LandUse feature dataset. Right-click on the LandUse feature class, and navigate to **Properties** | **Subtypes**. You have 10 subtypes. For every subtype, you will assign a domain and a default value for the SCAT field, as shown in the following table:

Subtype code	Description	Field	Default Value	Domain
0	Unknown		Unkn	dUnkn
11	Arable		А	dArable
12	Pasture	SCAT	P	dPasture
13	Meadow	SCAI	F	dMeadow
14	Vineyard		V	dVineyard
15	Fruit orchard		L	dFruitorchard

13. Click on Apply and on OK to save and close the Feature Class Properties dialog.

How it works...

The domains have been assigned to subtypes in the **Subtypes** section in the **Feature Class Properties** dialog. If your feature class doesn't have subtypes, you will assign the domains in the **Fields** section in the **Feature Class Properties** dialog box.

At step 8, the Arable subtype has been assigned the dArable domain for the **SCAT** attribute field. A good practice is to have similar names for subtypes and related domains. To be easier to read and make a distinction between the field name, subtype name, and domain name, put a small d, such as dArable, in front of the domain name. It is intuitive and easy to combine subtypes with different domains.

At step 3, choosing the right domain was a little tricky because the field is **BS** and the domain is dState. Another good practice is to keep your own documentation regarding the data type, code, and description for domains and subtypes. Another aspect is the default value for domains.

At step 7, you defined the default value for BM (Material), Brick value. When you add a Dwelling feature, the default values of the Material field will be Brick. Probably this will help the editing process, but sometimes it can be an illusory value. The user will not be more preoccupied with the correctness of this value. It would be a good idea to define as the default value for the Material field, code 0 (Unknown). This value will warn the user that it should be changed to this value according to the reality. There is no perfect solution for a default value, but your experience and the context of using geodatabase will help you to make the most appropriate decision.



There's more...

In the last step, you assigned only six domains to the LandUse feature class only if it defined 11 subtypes. There is another way to complete the domain list—by importing a feature class from another file geodatabase. When a feature class is imported, all the domains used by the imported feature class will also be added. Follow these steps to import the LandUse feature class from another file geodatabase, TOPO5000.gdb.

- 1. In Catalog Tree, right-click on the LandUse feature dataset, and navigate to Import | Feature Class (single). For Input Features, go to ... \Data\TOPO5000.gdb\ LandUse, and select the LandUse feature class. Click on Add. For Output Feature Class, type LandUseImport.
- 2. You will keep only two attribute fields: CAT (long) and SCAT (text). These fields are important because the first is a subtype field and the second field uses the subcategory domains for the Landuse feature class. You will delete all other attribute fields from the source feature class. In the Field Map (optional) section, select Zone (long), and select the X button on the right-hand side. Repeat the step for the remaining fields. Click on OK to close the Feature Class to Feature Class dialog.
- 3. Inspect the newly added domains in the **Database Properties** dialog for Topo5k.gdb. You now have five new domains: dForest, dHydrography, dTransportation, dOtherTerrains, and dUnproductive. Because you don't want to have a duplicate feature class, delete the LandUseImport feature class in ArcCatalog. The added domains still remain as file geodatabase properties.
- 4. Repeat step 12 from the *How to do it...* section to continue to add domains for the SCAT field, as shown in the following table:

Subtype code	Description	Field	Default Value	Domain
21	Forest		PD	dForest
31	Hydrography		Н	dHydrography
41	Transportation	SCAT	D	dTransportation
42	Other terrains		Cc	dOtherTerrains
51	Unproductive		Ν	dUnproductive

You can find the results of this section at ... Data DesigningGeodatabase Topo5k.gdb.

See also

► In the following *Creating a relationship class* recipe, you will go a step further in defining the behavior of a file geodatabase. You will create relationships rules between different feature classes.



Designing Geodatabase

Creating a relationship class

Relationships describe how the spatial/nonspatial objects are linked. In a geodatabase, the relationships are stored in relationship classes. In a relationship class, you can relate only two classes (table/feature class) from a geodatabase. Just as with a feature class, a relationship class can be created at the root level of a geodatabase or within a feature dataset.

In a relationship class, you have to decide the followings properties:

- Name of the relationship class
- Origin table and destination table
- Type of relationship, which can be as follows:
 - **Simple**: The objects can exist independently of each other and can have any type of cardinality.
 - Composite: The objects from a destination table/feature class (child) cannot exist without the objects from an origin table/feature class (parent); define the feature following and cascade, deleting behaviors (if an origin object is moved, rotated, or deleted, the destination object suffers the same actions); it can have only one-to-one or one-to-many cardinality.
- Label for origin and destination
- Message propagation (controls relationship behavior) with specific effects on composite relationships:
 - **Forward**: This includes cascade delete, feature following, and annotation update
 - **Backward**: This includes cascade delete and no feature following
 - **Both**: This includes cascade delete, feature following, and annotation update
 - None: This includes cascade delete and no feature following
- Cardinality (one-to-one, one-to-many, and many-to-many)
- Add an attribute in a relationship class to describe the relationship between objects
- The origin primary key (PK) and the destination foreign key (FK)
- The primary key and foreign key columns must have the same data type.

For more information about annotation concepts in the geodatabase context, please refer to *Chapter 6, Building Better Maps*.



You cannot modify the properties of an existing relationship class. You can delete and define it once again. If you delete one class (table/ feature class) that participates in a relationship class, the relationship class will be deleted too.

A table/feature class can be involved in more than one relationship class. Those multiple relationships for a table/feature class work well as long as they are coherently defined and don't generate contradictory behaviors. The last step in creating a relationship class is to define rules in order to refine the cardinality based on the subtypes of the feature classes/ tables. All types of cardinality support the relationship rules. A relationship rule is a property of the relationship class.

Getting ready

In this section, you will create two simple relationship classes and one composite relationship class between the LandUse feature class, BuildingsR feature class, and Owners table. Those relationships compose a stacked relationship because they link three classes in an open loop, as shown in the following screenshot:

		Composite	relationship		
Land	lUse	1	0*		lingsR
-OBJECTID : esriFieldTyp «SubtypeField» +CAT : e			-ToBuildings	-OBJECTID : esriFieldT -LandUseID : esriFieldT «SubtypeField» +BD : e	pelnteger (Foreign Key)
-ToLandUse	0*			0*	-ToBuildings
Simple	0*		vners	0*	Simple
relationship	-ToOwners	-OBJECTID : esriField +NameOwner : esriFie			relationship

When you define the cardinality, remember that term one can mean zero. For example, in the schema shown in the preceding screenshot, the Buildings (origin) are related to Owners (destination). The cardinality is many-to-many. The relationship allows the following situations:

- ▶ Building with no owner (1..0)
- ▶ Building with different owners (1..*)
- Owner with no building (0..1)
- Owner with any number of buildings (*..1)

Designing Geodatabase

How to do it...

Follow these steps to create two simple, many-to-many relationship classes:

- 1. Start ArcCatalog. In **Catalog Tree**, navigate to ...\Data\DesigningGeodatabase\ Topo5k.gdb\LandUse.
- 2. Right-click on the LandUse feature dataset, and select New | Relationship Class. For Name of the relationship class, type LandUseToOwners. For Origin table/ feature class, select the plus sign on the left-hand side of the LandUse feature dataset to see the LandUse feature class. Select the LandUse feature class. For Destination table/feature class, select the Owners table. Click on Next.
- 3. Select Simple (peer to peer) relationship, and click on Next. For the first relationship label, type ToOwners. For the second relationship label, type ToLandUse. Select the None (no messages propagated) option, and click on Next. Select the cardinality M-N (many-to-many) and click on Next. Select Yes, I would like to add attributes to this relationship class, and click on Next.
- 4. For FieldName, type OwnerProcent in the first empty row. Select Long Integer from the drop-down list. Select Yes for the Allow NULL values option, in the Field Properties section. As the primary key for the origin table, choose OBJECTID from the drop-down list, and as the foreign key, type LandUseID. As the primary key for the origin table, choose OBJECTID, and for foreign key, type OwnerID.
- 5. Click on **Next** to see a summary of your options, and select **Finish** to close the **New Relationship Class** wizard.
- 6. Right-click on the Buildings feature dataset, and select the **New | Relationship Class**. For **Name of the relationship class**, type BuildingsRToOwners. Repeat the previous steps, and set the relationship according to the following table:

Relationship	Value
Origin table/feature class	BuildingsR
Destination table/feature class	Owners
Type of relationship	Simple
Origin to destination label	ToOwners
Destination to origin label	ToBuildingsR
Message propagation	None
Cardinality	M-N (many to many)
Additional attributes	NO
Origin Table/Feature Class	Primary Key: OBJECTID
	Foreign Key: BuildingsRID
Destination Table/Feature Class	Primary Key: OBJECTID
	Foreign Key: OwnerID



Follow these steps to create a composite one-to-many relationship class between LandUse (as parent objects) and BuildingsR (as child objects):

- 7. Right-click on the LandUse feature dataset, and select New | Relationship Class. For Name of the relationship class, type LandUseToBuildings. For Origin table/ feature class, select the LandUse feature class. For Destination table/feature class, select the plus sign on the left-hand side of the Buildings feature dataset, and select the BuildingsR feature class.
- 8. Click on Next. Select Composite relationship (peer to peer) relationship and click on Next.
- 9. For the first relationship label, type ToBuildingsR. For the second relationship label, type ToLandUse. Select the **Forward (origin to destination)** option and click on **Next**. Select the cardinality 1-M (one-to-many), and click on **Next**.
- 10. Select NO, I do not want to add attributes to this relationship class and click on Next.
- 11. As the primary key, choose **OBJECTID** from the drop-down list, and as the foreign key, choose LandUseID.
- 12. Click on **Next** to see a summary of your options, and select **Finish** to close the **New Relationship Class** wizard.

Follow these steps to add rules for the LandUseToBuildings relationship class:

13. In **ArcCatalog**, double-click on the LandUseToBuildings relationship class to open a **Relationship Class Properties** dialog box. Select the **Rules** tab to see the subtypes for the LandUse and BuildingsR feature classes. You will define relationship rules, as shown in the following table:

BuildingsR subtypes	Cardinality (M)	Cardinality (M)
	Other terrains: 42	Unproductive: 51
Unknown	010	0*
Dwelling	02	0
Administrative buildings and socialcultural	03	0
Industrial and municipal	010	02
Historical sites, monuments, statues	02	0*
Dwelling annex	03	01

14. For Origin Table/Feature class subtypes, select Other terrains. For Destination Table/Feature class subtypes, click on the Code checkbox on the left-hand side of the Unknown subtype. Click on Unknown to select the subtype and to enable the Origin Cardinality and Destination Cardinality sections.



Designing Geodatabase

- 15. In the **Destination Cardinality** section, check the **Specify the range of associated destination objects** option. First, set the **Max** value by typing 10. Leave the **Min** value at 0.
- 16. For **Destination Table/Feature class subtypes**, click on the **Code** checkbox to the left of the Dwelling subtype. Click on Dwelling to select subtype and to enable the **Origin Cardinality** and **Destination Cardinality** sections.
- 17. In the **Destination Cardinality** section, check the **Specify the range of associated destination objects** option. First, set the **Max** value by typing 2. Leave the **Min** value at 0 according to the previous table. The first rule says that an Other terrains parcel subtype can have a maximum of two dwellings. You should see something similar to the following screenshot:

Relationship Class Properties		X
General Rules		
Origin Table/Feature Class subtypes:		
CodeDescription13Meadow14Vineyard15Fruit orchard21Forest31Hydrography41Transportation42Other terrains51Unproductive	Origin Cardinality □ Specify the range of associated origin objects Min: Max: □ □ ↓ V	
Destination Table/Feature Class subt Code Description Image: Omega of the structure of the struc	and s	
	OK Cancel Apply	



- 18. Select the **Administrative buildings subtype**, and check the **Specify the range of associated destination objects** option. For the **Max** value, type 3. For the **Min** value, type 0. This rule says that there must be between zero and three administrative buildings in a parcel (Other terrains).
- Continue to define the rules in Destination Table/Feature class subtypes for all building subtypes. For Origin Table/Feature class subtypes, select Unproductive. Leave unchecked the Unknown subtypes in the Destination Table/Feature class subtypes section to allow an unlimited number of Unknown buildings.
- 20. You will permit a maximum of two Industrial and municipal buildings and one Dwelling annex per Unproductive parcel. Select those subtypes from the Destination Table/Feature class subtypes section, and set the maximum value according to the previous table.
- 21. Finally, you will not permit a relationship with the rest of building types, such as Dwelling, Administrative buildings, and Historical sites. Select all those subtypes from the **Destination Table/Feature class subtypes** section, check the **Specify the range of associated destination objects** option, and set the maximum values to 0.
- 22. For the rest of the LandUse subtypes from **Origin Table/Feature class subtypes**, set the **Max** and **Min** values to 0. This will not permit BuildingsR to associate with parcel subtypes, such as Arable, Pasture, Meadow, Vineyard, Fruit orchard, Forest, Hydrography, and Transportation.
- 23. Click on **Apply** and on **OK** to save and close the **Relationship Class Properties** wizard.

You can find the final geodatabase schema at ... \Data\DesigningGeodatabase \ MyGeodatabaseResults\Topo5k.gdb.

How it works...

In the previous exercise, you used OBJECTID as the origin primary key field. But you could define your own primary key. The OBJECTID field guarantees a unique value for each record because it is managed by ArcGIS. You can't modify the OBJECTID values, and this can be inconvenient to maintaining the relationships when you are modifying feature geometry (for example: split, merge) or import features to another feature class.



For more details about the advantages and inconvenience of using the OBJECTID field as the primary key, please refer to Geodata/Data types/Relationships and related objects/Relationship class properties from ArcGIS Help (10.2) online.



Designing Geodatabase

There is a performance cost when you are working with relationship classes. The relationship classes will slow down the edit process because they must maintain the referential integrity in the geodatabase. A relationship class will assure that all changes you have made in the origin feature class/table will be reflected in the destination feature class/table according to the type and rules of the relationship.


At step 3, you created a many-to-many, simple relationship class between the BuildingsR feature class and the Owners table. A many-to-many relationship class requires an intermediary table that contains two key fields: origin primary key and destination foreign key. Both fields have a foreign key's role. You can see this table in ArcCatalog if you select the LandUseToOwners relationship class table. Select the **Preview** tab and the **Table** preview mode from the bottom of the **Preview** panel to examine the attribute fields.

There's more...

Follow these steps to test the relationship behavior:

- 1. Start ArcMap, and open an existing map document WorkingRelationships.mxd from ...\Data\DesigningGeodatabase. In **Table Of Contents**, you have two layers (BuildingsR and LandUse), two intermediate tables (LandUseToOwners and BuildingsRToOwners), and one non-spatial table, Owners.
- 2. Let's validate the relationship rules for the LandUseToBuildings composite relationship. Zoom in to the full extent of a map by selecting **Full Extent** in the **Standard** toolbar. Relationships are active and can be validated during an edit session.
- 3. In the **Editor** toolbar, select **Start Editing**. Select all features from BuildingsR and LandUse using the **Select Features** tool.
- 4. In the Editor toolbar, navigate to Editor | Validate Features. A message box will appear: 72 features are invalid. Click on OK to close. All invalid features are selected.
- Open the Attributes window by selecting the Attributes button in the Editor toolbar. You will see two layers: BuildingsR and LandUse. Select Expand All Relationships In Branch to see all selected features (blue bullets), related tables, and table records.

6. Let's inspect a relationship error. Click on **Bookmarks** and choose **Error2**. With the **Select Features** tool, select the **Others terrains** parcel with **LandUseID=1262**. In the **Attributes** window, expand the LandUse layer. You should see something similar to the following screenshot:



- Right-click on LandUse, and navigate to Selection | Open Table Showing Selected Feature to see the LandUse attribute table in the Show selected records mode. Navigate to Table Options | Related Tables, and choose LandUseToBuildingsR: ToBuildingsR. In the Editor toolbar, navigate to Editor | Validate Features. A message box will appear: The feature LandUse(subtype:Other terrains) has 4 related BuildingsR (subtype:Dwelling) features, thus violating the LandUseToBuildings relationships rule that specifies 0-2. Click on OK to close.
- To fix the error, delete two buildings. Select the parcel and the remaining buildings and validate features once again. The message box will tell you: All features are valid.



Designing Geodatabase

- 9. Let's check the feature following and cascade deleting behaviors of the LandUseToBuildings composite relationship. With the Select Features tool, select the Other terrains parcel with LandUseID=1262. In the Editor toolbar, select Edit Tool. Drag the parcel away from the previous location. The related buildings should follow the parcel. Select Rotate Tool. Rotate the parcel. The building should rotate, too. Delete the parcel using the Delete key. The buildings are deleted, too. Restore the features using Ctrl + Z.
- 10. In the Editor toolbar, select Editor | Stop Editing, and save your edit. Select File | Save as to save your map document.

See also

► To learn how to edit the features stored in feature classes and how to maintain the spatial relationships among them, please refer to Chapter 2, Editing Data. To learn how to create visual representation of the features from different feature classes on a map, please refer to Chapter 5, Working with Symbology, and Chapter 6, Building Better Maps.



2 Editing Data

In this chapter, we will cover the following topics:

- Editing features in a geodatabase
- Advanced editing in a geodatabase
- Creating geodatabase topology
- Editing geodatabase topology

Introduction

In the first part of this chapter, you will test different ArcGIS tools in order to add different types of feature geometry and their attribute values.

In *Chapter 1*, *Designing Geodatabase*, you constrained the attribute values using subtypes and domains. With the **Validation** option in an edit session, you can identify the invalid values in order to correct them.

You will continue to use the concept of validation in the feature geometry context in the second part of this chapter. You will constrain and administrate the spatial relationships between features with geodatabase topology. With the geodatabase topology, you will identify and fix the spatial errors from your Topo5k.gdb file geodatabase.

Editing features in a geodatabase

In ArcMap, a layer references the spatial datasets (for example, feature class and raster) that contain features with common geometry and attributes. A layer uses the dataset attributes to represent the features by one or more symbols. By default, a layer symbolizes features from a feature class using the subtype field.

www.allitebooks.com

Editing Data -

The editing session in ArcGIS for Desktop is based on layers. When you start an edit session, you have to define the **Feature Template** that describes the type of feature that you intend to create. ArcGIS creates feature templates by default, based on the layer symbology. In the **Creating Feature** window, you can see the list of feature templates. You can create new types of features with the **Organize Feature Templates** option. Moreover, you can define a default attribute for one type of feature or for all types of features from a layer. When you create a new feature, the default attribute is automatically inherited. Choosing a default value works for subtypes and domains, too.

After you create a feature, you should edit its attributes using the **Attribute** window. Most of the attribute fields will automatically get completed according to the default subtype and domains you already defined in the *Using subtypes and domains together* recipe of *Chapter 1*, *Designing Geodatabase*.

Getting ready

In *Chapter 1*, *Designing Geodatabase*, you learned how to create the Topo5k.gdb file geodatabase schema. Now, it's time to add data. There are several ways to add data into a geodatabase:

- Using the Import/Export and Load Data options in ArcCatalog
- Using the Load Objects option in an ArcMap environment
- Creating new features by screen digitizing and by editing existing ones
- Using the Export Data option in an ArcMap environment

In this recipe, you will work with the **Editor**, **Snapping**, and **Edit Vertices** toolbars to create new features and to edit the existing features. The LandUse and BuildingsR feature classes already contain features. The features were digitized based on a scanned topographic map at scale 1:5,000 produced in 1995.

As a base layer for updating features, you will use an orthophotography from 2012 corresponding to a map at scale 1:5,000. The orthophoto map has a resolution of 1 pixel =0.5 meter and is stored as **Raster Dataset** in the Topo5k.gdb geodatabase.

Even if you assume that you are already comfortable with the elementary edit process in ArcGIS 10, please remember the main steps:

- 1. Start the edit session.
- 2. Set the snap environment (optional).
- 3. Before starting a sketch, choose a feature template and a construction tool.
- 4. Create the new feature.




- 5. Add or modify attribute values of the feature.
- 6. Save edits.
- 7. Stop the edit session.

How to do it...

You can follow these steps to edit features in a geodatabase:

- Start ArcMap, and open an existing map document Editing.mxd from <drive>:\ PacktPublishing\Data\EditingData. Notice that layers from the Table Of Contents section are symbolized based on their subtypes. The LandUse layer has defined a transparency. Right-click on the LandUse layer, and navigate to Properties | Display. You will notice that Transparent has a 60 percent value. Let's add a popup label with the OBJECTID value in the data view. Check Show MapTips using the display expression, and choose the desired field. Click on OK.
- 2. From the **Bookmarks** menu, select **Create a Fish Pond**. You will create a new feature in the LandUse layer, as shown in the following screenshot:



- 3. In the **Table Of Contents** section, right-click on the LandUse layer, and navigate to **Edit Features** | **Start Editing**. In the **Editor** toolbar, navigate to **Editor** | **Editing Windows**. In the **Create Feature** window, you will see the feature templates for all layers that are visible in the **Table Of Contents** section.
- 4. In the **Editor** toolbar, navigate to **Editor** | **Snapping**, and check the **Snapping** toolbar. In the **Snapping** toolbar, select only **Vertex Snapping**. Snapping options assure the coincidence of new feature coordinates with the coordinates of existing features.
- 5. In the Editor toolbar, navigate to Editor | Options | Attributes. Navigate to Display the attributes dialog before storing new features | For the following layers options | LandUse. Click on OK. Every time you create a new LandUse feature, the Attribute window will show up after you have finished the sketch.
- 6. Select the feature with **OBJECTID** as 755 from the LandUse layer. In the **Editor** toolbar, select the **Cut Polygons Tool** option to cut the arable polygon.
- Select the Trace tool. Right-click on the polygon, and select Trace Options. In the Trace Options dialog, type 5 as the Offset value, select the Trace selected features option, and click on OK.
- Use the screenshot from step 2 to follow the edit steps. Start the sketch from point

 (1) and finish it at point
 (2). Right-click on point
 (2) to choose a value for the Length field, type in 84, and close the window. Move the segment towards point
 (3), and add the end of the curve to point
 (4).



While you are sketching, press *Tab* to display the **Feature Construction** toolbar.

9. Again, go to point (2), and right-click on it to choose a value for the **Length** field, type in 61, and close the window. Move the segment to point (5), and add the last vertex to point (6). To finish the sketch, use the *F2* shortcut key.

- 0 X Q Editing.mxd - ArcMap Attributes File Edit View Bookmarks Insert Selection Geoprocessing 🗋 🚰 🔚 🚔 | % 🗊 🛍 🗶 | 🄊 (🍽 🔶 🗸 | 1:4,000 🗄 🚸 LandUse 🔍 🔍 🖑 🥝 | 💥 🖸 | 🗢 🔶 | 🔯 - 🖾 | 👠 🚳 🥖 👘 Ţ ÷ E 📩 🗉 Arable - Fish pond 🚸 BuildingsR - ToBuildingsR Table Of Contents Ψ× Owners - ToOwners 🗞 🧵 📚 📮 🗉 🗄 🗉 🛛 Owner1 🗉 🖶 Buildings * 🗄 🚸 BuildingsR - ToBuildings 🛓 🗉 Satisfying 😑 🖶 LandUse 🕀 🔽 LandUse **^** = Owners 1324 💷 Lan Category Ε Hydrography H:\PACKT_PUBLISING SubCategory Fish pond Crthonhoto5k LandUseID 1324 OBJECTID Table - LandUse 🛐 Catalog Attributes 🗄 + | 🖶 + | 🖳 🌄 🖸 🐠 🗙 | 🍢 🖓 🖓 🗙 LandUse Owners × OBJECTI NameOwner OBJECTID SHAPE * Category SubCategory LandUseID SHAI ٨ 755 Polygon Arable Arable 755 31 14 - 4 3 F FI _ h (1 out of 100 Selected) H 📄 🥅 🥒 (2 out of 647 Selected) I4 - 4 0 + Owners LandUse uildingsR LandUseToOwner × OBJECTID * SHAPE * Destination Mat OwnerProcen RID * LandUseID * OwnerID * ~ Polygon Dwelling an 39 <Null> 30 845 10 45 Polygon Dwelling 33 755 50 <Null> <Nul> 34 755 10 I4 - 4 0 F FF 41 1324 1 ÷ H 📄 🗖 (4 out of 29 Selected) (8 out of 477 Selected) I4 - € 0 + LandUseToOwners BuildingsR

Next, you will edit the attribute fields for the new polygon feature, as shown in the following screenshot:

- 10. In the **Attributes** window that automatically opens, select the new LandUse feature you just created. The default value for **Category (CAT)** and **SubCategory (SCAT)** is Arable. You defined the default values in the Using subtypes and domains together recipe of Chapter 1, Designing Geodatabase.
- 11. Let's change the attribute values. Select the Category field, and click on the small button from the right to open the Choose Symbol Class window. Select the Hydrography value, and click on OK. For the SubCategory field, select the Fish pond value from the drop-down list. For LandUseID, type the value of OBJECTID. Click on OK to close the window.



Editing Data

- 12. Return to the **Attribute** window, and expand the nodes for the Fish Pond feature to see the relationships. The new LandUse feature is related to the BuildingsR layer (BuildingsR-ToBuildingsR) and Owners table (Owners-ToOwners). Select the Owners-ToOwners relationship to define the owners of the parcel.
- 13. Right-click and navigate to **Table | Open Attribute Table**. In the Owners table, select the owner with NameOwners as Owner1. At this point, open the attribute tables for the LandUse and BuildingsR feature classes and for the LandUseToOwners relationship. To see LandUseToOwners and BuildingsRToOwners relationship tables and the Owners nonspatial table, click on the List By Source button in the Table Of Contents section.



To see the tables as shown in the preceding screenshot, click on the tab of the LandUse table and drag it within the **Table** window. When you see the **Dock** icon, drag the selected table to the right or down docked position.

14. Return to the **Attribute** window, and right-click on the LandUse feature relationship: Owners-ToOwners. Select **Add Selected**. Now, your parcel has an owner with **OBJECTID** as 1.

You should check the relationship class table named LandUseToOwners; it stores the relationship between Fish Pond and Owner1.

15. In the Table window, select the LandUseToOwners table to check the changes. Edit the OwnerProcent attribute field with its value as 100. Select and inspect the Owners table. To see how many parcels and buildings own the Owner1 table, click on the Related Tables button, and choose the two relationships one by one: LandUseToOwners:ToLandUse and BuildingsRToOwners:ToBuildingsR.

Next, you will create a new parcel and modify two vertices of a dwelling. In the following screenshot, you have all elements to create a new parcel by splitting the arable polygon:

Chapter 2



- 16. Click on Bookmarks, and select Cut a Parcel and modify a Building.
- 17. Select the parcel with **OBJECTID** as 755 from the LandUse layer.
- 18. First, go to the **Snapping** toolbox and keep only the **Vertex Snapping** option selected.
- 19. Second, select the **Cut Polygons Tool** option. Start the sketch from point (1) and select the **Distance-Distance** tool. Click on point (1) as a center for the first circle, and press the *D* key to type 77 for **Distance**. Click on point (2) as a second center, and press the *D* key to type 139 for **Distance**. You have obtained a point as an intersection of two circles. Click on the first intersection to obtain the second vertex of the cutting polyline.
- 20. Again, select the **Distance-Distance** tool. Click on point **(2)** as a center for the first circle, and press the *D* key to type 128 for **Distance**. Click on point **(3)** as a second center, and press the *D* key to type 135 for **Distance**. Click on the second intersection to obtain the third vertex of the cutting polyline.
- 21. Select **Straight Segment**, and click on point **(2)**. To finish the cutting sketch, press the *F2* shortcut key.
- 22. In the **Attributes** window, select the following values: **Category** as Other terrains, **SubCategory** as Built-up area, and for **LandUseID**, type the value of **OBJECTID**. Click on **OK**.




Editing Data -

23. The new LandUse feature is related with the BuildingsR layer (BuildingsR-ToBuildingsR) and the Owners table (Owners-ToOwners). Try to manage those relationships by yourself. How to start? Firstly, with Shift pressed, select the building with the **Select Features** tool. Secondly, select BuildingsR-ToBuildingsR, and right-click on it to choose the **Add Selected** option.

Next, you will correct the position of two vertices of the building according to the orthophoto map used as a background:

24. Keep the building selected and with the *Shift* key pressed, unselect the parcel. Click on **Edit Vertices**, and from the toolbar, choose **Modify Sketch Vertices**. Select the two vertices by drawing a small box around the vertices. Drag the selected segment, and drop it as shown in the preceding screenshot.

Finally, you will correct a neighboring LandUse parcel. You have two options, as shown in the following screenshot:



44

- 25. Use the **Reshape Feature Tool** option to draw a line as point **(1)** from the preceding screenshot in order to cut the polygon with **OBJECTID** as 755 from the LandUse layer. You have created a gap between the parcels. To modify the parcel from the left-hand side, select the **Other Terrains** option with the **Auto Complete Polygon** construction tool from the **Create Feature** window. Put the first vertex in the gap and the second in the neighboring parcel—see point **(2)**. With the **Select Features** tool, select both the parcels, and from the **Editor** toolbar, select **Merge**. In the **Merge** dialog, select **Build-up area (LandUse)**, and click on **OK**.
- 26. Use the Cut Polygons Tool option to split the polygon. With the Select Features tool, select the two parcels from point (3). From the Editor toolbar, select Merge. In the Merge dialog, select Build-up area (LandUse), and click on OK.
- 27. In the **Editor** toolbar, navigate to **Editor** | **Stop Editing**, and save your edit. Navigate to **File** | **Save As**, and save your map as MyEditing.mxd.

You can find the final results at <drive>:\PacktPublishing\Data\EditingData\ MyEditingResults\Editing.mxd.

How it works...

To select an existing parcel from the LandUse layer, and in order to edit it, first use the **Select Features** tool, and after that, select the specific edit tools from the **Editor** toolbar. If you use an **Edit** tool to select a feature, there is always a risk that you will create a subtle movement of the selected feature. A small shift will create overlaps and gaps between the coincident features. To protect features from this small shift, navigate to **Editor | Options | General | Sticky move tolerance**, and set a minimum distance for cursor movement before the selected feature will be moved too.

At step 23, we tested the multiple vertex editing. We have selected two vertices and moved them at once.



You can change the geometry of a segment by selecting two vertices. Right-click on the segment, select **Change Segment**, and choose one of the options: **Bezier** or **Circular Arc**.

You can also delete multiple vertices at the same time.

Editing Data

In the Creating a relationship class recipe of Chapter 1, Designing Geodatabase, we created relationship rules between the LandUse, BuildingsR, and Owners tables. We have already noticed at step 12 that relationships are active and must be updated every time we add new features. The relationship rules can be validated during the edit session. Select all features from BuildingsR and LandUse using the **Select Features** tool. In the **Editor** toolbar, navigate to **Editor** | **Validate Features**. A message box will appear stating **72 features are invalid**. Click on **OK** to close. All invalid features are selected. In the **Attributes** window, inspect and try to correct the errors yourself.

There's more...

To add more data to your geodatabase schema, we will test two more options: **Load Data** using ArcCatalog and **Load Objects** in the ArcMap environment. Follow these steps to add the data in the geodatabase file using **Load data**:

- Start ArcMap, and open the existing Editing.mxd map document from <drive>:\ PacktPublishing\Data\EditingData.
- 2. Open the Catalog window from the Standard toolbar to have access to your data. In the Catalog window, right-click on WatercourseL from ...\EditingData\ Topo5k.gdb, and navigate to Load | Load Data. Set the following parameters from panels:
 - □ The Input data parameter as the ... \Data\TOPO5000.gdb\ Hydrography\ WatercourseL feature class; click on Add
 - Check I do not want to load all features into a subtype
 - Target Field (destination) and Matching Source Field (source):

```
HYC[int] = HIC[int]
Name[string] = Name[string]
HType[int] = HAT[int]
```

- Check Load all of the source data
- Click on Next and Finish. In the Table Of Contents section, right-click on WatercourseL, and choose Zoom To Layer to see the polyline features.

Continue to follow the steps to populate the Watercourse feature class with features from the **LandUse** feature class using **Load Objects** in ArcMap.

4. To add the Load Objects tool, click on the drop-down arrow from the right-hand side of the Editor toolbar, and select Customize. Select Commands, and for Show commands containing, type load objects. From Commands, click and drag the Load Objects option to the Editor toolbar. Click on Close. To use this tool, you need to start the editing session.

46

- 5. Before starting an edit session, in the Table Of Contents section, right-click on Watercourse, and navigate to Edit Features | Organize Feature Templates. You will define a default value for the Name field. All the new features from Watercourse that you add in this edit session will have the Name field as River Flake. In the Organize Feature Templates window, select Watercourse from the Layers section. With the Ctrl key pressed, select the River and Stream templates. Click on Properties, and for Water Name, type River Flake. Click on OK and then on Close.
- 6. Start the edit session from the Editor toolbar by navigating to Editor | Start Editing.
- 7. In the **Table Of Contents** section, right-click on Watercourse, and select **Load Objects**. Set the following parameters from panels:
 - The Input Data parameter as the ...\Data\EditingData\Topo5k.gdb\ LandUse\LandUse feature class; click on Add
 - The Target field as the Stream subtype
 - Accept the default matching Target Field (destination) and Matching Source (source)
 - Check Load only the features that satisfy a query
 - Click on **Query Builder** and build the following expression:

CAT=31

- Accept all the other default parameters
- 8. Click on Finish. In the Table Of Contents section, right-click on Watercourse, and choose Zoom To Layer.
- 9. Select all vectors using the Select Features tool from the Tools toolbar and open the Attributes window. All nine Stream features have the same attribute value for the HYC field as Intermittent. This is because in the Using subtypes and domains together recipe of Chapter 1, Designing Geodatabase, we have assigned the domain code 2 (Intermittent) as the default value of the HYC field for the Stream subtype features.

Let's suppose that we mistakenly chose to load all objects in the **Stream** subtype. To change the subtype value to River for all the nine features at the same time, select the Watercourse layer in the **Attributes** window. Click on the icon from the left Stream value to open the **Choose Symbol Class** window. Select the River value, and click on **OK**. Read carefully the warning message, and select **Yes** to automatically assign the corresponding Perennial default values for **HYC**. The **Name** field already has the River Flake value. Notice that every feature has the same **HType** and **HYC** and the **Name** value. In the **Editor** toolbar, navigate to **Editor** | **Stop Editing**, and save your edit. Navigate to **File** | **Save As**, and save your map as Editing.mxd. You can find the final results in <drive>:\PacktPublishing\Data\EditingData\ MyEditingResults\Topo5k.gdb.



Editing Data

Recall that you constrained the attribute values by subtypes and domains in *Chapter 1*, *Designing Geodatabase*. Every time you load features from other sources, such as existing feature classes or shapefiles, don't forget to validate the attribute values during the edit session. The **Validate Features** option will identify all the invalid values for the attribute fields for which you have already defined the subtypes and domains. All features that have invalid values will be selected. You should inspect and correct the reported errors with the **Attributes** window.

See also

► In the next recipe, Advanced editing in a geodatabase, you will continue to work with advanced editing tools and with **COordinate GeOmetry** (**COGO**)

Advanced editing in a geodatabase

The **Advanced Editing** toolbar offers tools to reshape and replace geometry, correct the overshoot or undershoot errors, split line features in intersection, divide a line or curve based on specified lengths or percentages, and edit multipart features.

The **COGO** toolbar allows you to work with **COoordinate GeOmetry**. Coordinate geometry refers to directions or bearings, angles, and horizontal distances that generally came from a topographic survey and that describe a series of consecutive lines. Those lines can be straight lines or simple curves and are named as **courses** or **2-point line**. A course has only two vertices. The survey measurements that describe the courses can be stored in a traverse file in the context of ArcGIS. From the topography point of view, a traverse is a classical method for a detail topographic survey of an area. In ArcGIS, in a closed traverse, the consecutive lines start from a known point and end at the same or another known point. In an open traverse, the consecutive lines start from a known point and do not end at a known point. By known point or control point, we mean a fixed (ground) point of known *X* and *Y* coordinates.

With the **Create COGO Fields**, **Update COGO Attributes**, and **Construct 2-Point Line** tools from the **COGO** toolbar, you can add, calculate, and update the COGO attributes for an existing feature class.




For theory and worked examples about azimuth, bearings, horizontal distances, types of curves, and simple two-dimensional traverse computation, please refer to:

Principles of Geospatial Surveying, Artur L.Allan, Whittles Publishing, 2007, Technical Procedures, pp.7-18, Survey Computations, pp.145-150, and Construction and Curves, pp.240-244.



Getting ready


In this recipe, we will work with the RoadL layer to create new features using the **Midpoint** tool and to edit the existing features using the **Line Intersection** and **Extent** tools. You will add new attribute fields to the RoadL layer using the **Create COGO Fields** tool in ArcCatalog. Finally, you will update some parcels from the LandUse layer based on the coordinate geometry coming from a computed traverse. You will use a 2D closed-loop traverse. The line segments are described by direction, which is expressed relative to **North Azimuth**, and by horizontal distance, as shown in the following screenshot:



49 —

Editing Data

The curves from your traverse are circular curves with constant radius. In the context of ArcGIS, curves are defined by arc, radius, chord direction, and side (**Curve 6**) or by arc, radius, and side when you already know the start point and direction for a tangent and don't need to specify the chord direction and tangent (**Curve 10**). You can calculate the rest of the elements that describe a simple curve, such as **Angle**, **Chord Distance**, or **Tangent Length**, using the **Curve Calculator** from the **COGO** toolbar, as shown in the following screenshot:




How to do it...

Follow these steps to update the RoadL layer:

- 1. Start ArcMap, and open an existing map document AdvancedEditing.mxd from <drive>:\PacktPublishing\Data\EditingData.
- 2. From the Bookmarks menu, select Create Field road. In the Table Of Contents section, right-click on the RoadL layer, and navigate to Edit Features | Start Editing. Add the Advanced Editing and COGO toolbars. In the Create Feature window, select the Field road template. In the Snapping toolbar, select only Vertex and Edge Snapping. In the Editor toolbar, select the Midpoint tool to create a centerline based on the Transportation subtype from LandUse, as shown in the following screenshot:



Chapter 2




- Click on point (1), and then click on point (2), to add the first vertex of the sketch at the midpoint between point (1) and point (2). To add another vertex, click on points (3) and (4). Those points are on the edge of the LandUse polygon. Continue to add vertices to the end of the road.
- 4. To connect Field road with Rural road (point (5)), and to split Rural road at the intersection, let's use the Line Intersection tool from the Advanced Editing toolbar. Select Field road and the Line Intersection tool. First, click on the end of the selected feature (red circle from the preceding screenshot), and secondly click on point (5). Press O to choose the Extend existing feature option, and click on OK. Finally, click again on point (5). Click on Undo Line intersection to undo the last action.
- 5. You will test another way to split Rural road and to correct undershoots. First, to specify the feature that you want to connect to, select the Rural road. Secondly, select the Extent tool. Finally, click on Field road to specify what vector you want to extend to Rural road (red circle from the preceding screenshot). To split Rural road at the intersection, select the Split tool from the Edit toolbar, and click on point (5).
- 6. Save and stop the edit session. Save the map document at ... \Data\ EditingData as MyAdvancedEditing.mxd.

Let's add new features to the RoadL layer using COGO:

Editing Data

- Open ArcCatalog. Click on the drop-down arrow from the right-hand side of the Standard toolbar, and navigate to Customize | Commands. In Show commands containing, type cogo. Select the Create COGO Fields tool, drag-and-drop it on the Standard toolbar. Select the RoadL feature class, and click on the Create COGO Fields tool to add the specific COGO fields. Close ArcCatalog, and open MyAdvancedEditing.mxd.
- It's time to specify the angular units. In the Editor toolbar, navigate to Editor |
 Options | Units. In the Angular Units section, choose North Azimuth for Direction
 Type and Gons for Direction Units. In Display angles using, type 4 for decimal places. Click on OK.
- 9. Start an edit session. In the **Table Of Contents** section, right-click on the RoadL layer, and select **Open Attribute Table**. Inspect the COGO fields that were created. Leave the **Table** window open.
- 10. We will transform **polyline 1** and **polyline 2** into COGO lines and add a new **2-Point Line** as shown in the following screenshot:




11. Let's consider **polyline 1** coming from an old survey taken in the field and **polyline 3** coming from screen digitizing. To differentiate those two polylines, we will transform **polyline 1** into COGO lines. Select **polyline 1**, and click on the **Split into COGO lines** tool from the **COGO** toolbar. Click on **Template**, choose Field road as the feature template, and click on **OK**. To calculate the coordinate geometry for the newly created lines, select the **Update COGO Attributes** tool. Inspect the changes in the **Table** window.



- 12. Let's add a COGO curve starting from point (1) as shown in the preceding screenshot. From the Bookmarks menu, select Create a COGO curve, then select Construct 2-Point Line, and finally select polyline 2. The black arrows indicate the direction of the vector. Choose the curve with the Chord field of 100 meters, the Angle field of 482 gons, the Chord Direction field of 285 gons, and the Turn field of Right to obtain a curve. In the Reference section, navigate to Use selected line | Start Point. Click on Create to obtain Case 1. We expected to obtain a curve from point (1), but the line started from polyline 3.
- 13. Select the Edit Vertices option from the Edit tool to see the direction of the vector. The red vertex indicates the end of the vector. To reverse the direction, right-click on the selected vector, and choose Flip.
- 14. Repeat step 7 to obtain Case 2. Click on Create and close the window.
- 15. To calculate the coordinate geometry for the newly created curve, select the **Update COGO Attributes** tool, inspect the changes in the **Table** window, and save the edits.

Let's update a LandUse parcel using the **Traverse** tool:

16. From the **Bookmarks** menu, return to **Create Field road**. In the **Table Of Contents** section, check the LandUse layer to see the feature templates in the **Create Feature** window. In the **List by Selection** mode, set only the LandUse layer as the selectable layer and return to the **List by Source** mode. Select the parcel as shown in the following screenshot:



Editing Data _

- 17. We will replace the existing parcel with a new one using the survey recently taken in the field. We will consider that traverse from the Parcel_Ownerl.txt file was already adjusted for a closure error. Select the **Replace Geometry Tool** option from the **Advanced Editing** toolbar. Select the **Traverse** tool from the **COGO** toolbar. Right-click on the **Traverse** window, and select **Load Traverse**. Go to ...\Data\ EditingData, and select the Parcel_Ownerl.txt file. Click on **Finish**, and close the window.
- 18. Examine the spatial errors. Notice there are some overlaps and gaps between the parcels. Let's try to correct some errors. Select the **Align To Shape** tool from the **Advanced Editing** toolbar. Follow the options and steps from the following screenshot:

Start buffer	Align To Shape
	Alignment shape (1)
a Eine	Click to trace the shape that layers will be aligned to.
	Layers to be aligned
SAL RECTOR	Choose one or more layers to align to the shape.
	☐ � RoadL ☑ � LandUse
	Align selected features (1 features selected)
	Align selected features (1 features selected)
	5 (2) Meters
and the second	Insert vertices to preserve original shape of geometry outside alignment tolerance.
	About aligning features (S) Align Close
	Finish buffer



- 19. With the trace tool, start from the first point (Start buffer), and define a short segment on the edge of the updated parcel. To finish the trace and return to the Align To Shape window, double-click on the last point (Finish buffer). Try to change the value of Tolerance to see how the buffer changes. Next, click on Align to modify the edges of the neighboring parcels. Then, continue to align the parcel by updating the Tolerance value. Finally, click on Close to close the window. Inspect the attributes of the new parcel. The attributes remain unchanged because of the Replace Geometry Tool option.
- 20. Save the edits, and stop the edit session. Save the map document to ... \Data \ EditingData as MyAdvancedEditing.mxd.

You can find the final results at <drive>:\PacktPublishing\Data\EditingData\ MyEditingResults.

How it works...

Regarding step 3, it is not necessary to have an existing feature to define the line segment. We just indicate the two points directly on the orthophoto map.

To store the COGO in the attribute table of the RoadL layer, we created empty COGO fields in ArcCatalog with the **Create COGO Fields** tool. By adding a COGO curve, we have emphasized the importance of digitized direction.

We used the **Replace Geometry Tool** option from the **Advanced Editing** toolbar in order to keep the attributes of the LandUse parcel and its relationship with the Owner table.

After we updated the parcel at step 11, we corrected the edges of the neighboring parcels in order to maintain the adjacency between the surrounding parcels. Using the **Align To Shape** tool is a right decision because we assumed that horizontal positions and dimensions of the new parcel are more accurate than manual digitized parcels.

See also

 In the next recipe, Creating geodatabase topology, we will learn how to create and validate the spatial relationships between features in a file geodatabase

Creating geodatabase topology

In a map, topology refers to spatial relationships between features, such as:

 Connectivity: This indicates that rivers from the WatercourseL feature class or roads from the RoadL feature class should be connected



Editing Data

- Coincidence: This indicates that the water and roads from the Watercourse and Road polygon feature classes should be covered by the Hydrography and Transportation subtypes from the LandUse feature class
- Adjacency: This indicates that parcels from LandUse have common edges and should not overlap or have gaps
- Containment: This indicates that buildings from the Buildings feature class should be within the Other Terrain (Built-up area) Subtype from the LandUse feature class

In the ArcGIS context, a topology is a collection of rules that define the spatial relationship between features within a feature class or between features of two or more feature classes belonging to the same feature dataset.

A topology is stored in a file geodatabase as an individual File Geodatabase Topology element. In a topology, we can apply one or more rules to a feature class. We can apply different rules to the feature subtypes. We can create different and complicated spatial relationships between subtype features of one, two, or more feature classes in a single topology.

In a topology, if we want to define topological rules between features of two or more feature classes belonging to different feature datasets, we have to move them in the same feature dataset. We can have more topology elements in a feature dataset, but a feature class can be implicated in only one topology at a time.



For more details regarding topology and topology rules, please refer the online *ArcGIS Help* (10.2) by navigating to **Geodata** | **Data types** | **Topologies** at http://resources.arcgis.com/en/help/main/10.2.

Getting ready

The main steps involved in creating a topology are:

- 1. Name the topology.
- 2. Set Cluster Tolerance.
- 3. Add one or more simple feature classes.
- 4. Define the **Ranks** (importance).
- 5. Add one or more **Rules**.
- 6. Create the topology in a feature dataset.
- 7. Validate the topology.



Cluster tolerance is the distance range where the feature vertices are considered coincident. Starting from classical cartographic theory, let's consider that absolute accuracy of our dataset at scale 1:5,000 is 0.5 meter. We will use a cluster tolerance of about 0.5/10 = 0.05 meter.


Ranks define what feature vertices will be moved during the validation process.

After we define the topology rules between four feature classes from the Topo5k.gdb geodatabase, we will validate the topology in order to apply the rules to our feature classes.

How to do it...

Follow these steps to create File Geodatabase Topology in a file geodatabase using the ArcCatalog context menu:

- Start ArcCatalog. In the Catalog Tree section, go to <drive>:\PacktPublishing\ Data\EditingData, and select Topo5k.gdb. Expand the Buildings and LandUse feature datasets.
- 2. To create a topology for the BuildingsR and LandUse feature classes, we have to add them in the same feature dataset—LandUse—as shown in the following screenshot:





Editing Data -

3. Select the BuildingsR feature class from the Buildings feature dataset, and drag-and-drop it in the LandUse feature dataset. Right-click on the LandUse feature dataset, navigate to New | Topology, and click on Next. Leave the default value for Enter a name for your topology. For Enter a cluster tolerance, type 0.05, and click on Next. Click on Select All to check all feature classes, and click on Next. Define the relative importance of the feature classes by selecting the following ranks from the Rank drop-down list: BuildingsR = 1 and LandUse = 2. Click on Next to see the following panel:

- BuildingsR	New Topology			×
Unknown Dwelling Administrative buildings and	Specify the rules for	the topology:		Close
Industrial and municipal	Feature Class	Rule	Feature Class 🔺	Add Rule
Historical sites, monuments, st Dwelling annex LandUse Unknown Arable m	BuildingsR : A BuildingsR : In BuildingsR : Hi	Must Not Overlap Wi Must Be Covered By Must Be Covered By Must Be Covered By Must Be Covered By Must Be Covered By	LandUse : Hyc LandUse : Oth LandUse : Oth LandUse : Oth LandUse : Oth LandUse : Oth LandUse : Oth	Remove
BuildingsR LandUse Unknown Arable Pasture E	BuildingsR LandUse LandUse	Must Not Overlap Must Not Have Gaps Must Not Overlap	-	Load Rules
- Meadow - Vineyard - Forest - Hydrography - Transportation - Other terrains +			< <u>B</u> ack Next	> Cancel

4. Select the **Add Rule** button. We have three sections: **Features of feature class**, **Rule**, and **Feature class**, as shown in the following screenshot:

Add Rule	fager in	×
Eeatures of feature class: BuildingsR : Dwelling annex Image:	Rule Description	The area features of one layer must cover the area features of another layer. Any area where features in the first layer are not covered by features in the second layer is an error.
		OK Cancel



- 5. In the first and third sections, we can see the feature classes and their subtypes. This will allow us to define rules at feature subtype levels. In the second section, we have a drop-down list with the topology rules corresponding with the type of geometry. In the Add Rule window, we can define topology rules for a single feature class or between two feature classes. Click on Cancel to return to the New Topology window.
- 6. Select the Load Rules button to add a set of rules: Rule Set (*rul format). Go to ...\Data\EditingData, select the LandUse_Topology.rul file, and click on Open and on OK to load the rules.
- 7. Inspect the rules. We don't have a general rule between all subtypes from Buildings and LandUse. As we can see, the rules refer to the Buildings and LandUse subtypes. In this way, we can exclude some feature subtypes from following a rule that applies to all other subtypes from the parent feature class. To exclude a feature subtype, just avoid mentioning it in the list (for example, the BuildingsR:Unknown subtype). Click on **Next** and on **Finish**. Select **No** in the popup window that appears. You will validate the topology in the next step.
- 8. In ArcCatalog, select LandUse_Topology, and choose the **Preview** mode to see the topology errors. You will see a blue hatched rectangle. This means that the whole area is not validated and requires topology validation in order to find the errors. This area is called a *dirty area*.
- 9. We can check the topology status in ArcCatalog. Right-click on the LandUse_ Topology element, and navigate to the **Properties** | **General** tab. The topology status is Not Validated.
- 10. Let's validate the topology to identify any errors. Right-click on the LandUse_ Topology element, select Validate, and from the View menu, select Refresh to see changes in the **Preview** mode. Now the topology status is Validated-Errors Exist.
- 11. Right-click on the LandUse_Topology element, navigate to the **Properties** | **Errors** tab, and click on the **Generate Summary** button to inspect the errors. You can save the report in a .txt file.



The **Must be larger than cluster tolerance** rule is added by default. We cannot remove this rule as it is applied automatically to all features participating in a topology.

Every time we make changes in a topology (add/delete rules or cluster tolerance), the entire area covered by our features will become a *dirty area*. When we edit the features (for example, change subtypes and add/delete features or vertices), the area surrounding the features will need additional topology validation and will also be considered as a *dirty area*.

Editing Data

- 12. You can change the value of **Cluster Tolerance** to see changes in topology status and in the **Preview** mode.
- 13. If you want to add more rules, open the **Properties** tab of LandUse_Topology, and navigate to the **Rules** | **Add Rule** button. Add the rules and validate the topology. Close ArcCatalog.


You can find the final results at ... \Data\EditingData\MyTopologyResults.

How it works...


A topology has one of the following statuses:

- Not Validated
- Validated-Errors Exist
- Validated-No Errors
- ▶ If you edit the features, Not Validated with dirty area

A topology is not applied to our data until we validate it. Validation helps us to find errors. Validation generates two processes: cracking and clustering. The connected features are disconnected and connected again by adding/deleting vertices and slightly moving feature vertices based on the cluster tolerance and ranks. In the example from the following screenshot, we exaggerated the value of **Cluster Tolerance** to 1 meter for the LandUse topology before the validation process:







Notice in the following screenshot how the vertices were deleted (v1) and moved (v2) after the topology validation:

For more details about the cracking and clustering processes, please refer to the Esri Technical Paper (2010): *Understanding Geometric Processing in ArcGIS*.



If you validate a topology in ArcCatalog, you cannot reverse the effects of the validation process.

If you validate a topology in ArcMap, you can undo the changes made through the validation process.

See also

 In the next recipe, Editing geodatabase topology, we will display, analyze, and fix the spatial errors in ArcMap

61 —

Editing geodatabase topology

It's very important to have a comprehensive understanding of our dataset and the spatial relationships between features before choosing the right rules for a topology and the right solution to correct the errors. When you inspect the error, firstly identify the features involved, secondly understand what is causing the error from a geometrical point of view, and thirdly use the proper solution. There are different solutions to the same error:

- Use a predefined fix
- Combine a predefined fix with manual edits
- Manually edit features



For more details about the editing topology, please refer to the online *ArcGIS Help* (10.2) by navigating to **Desktop | Editing | Editing topology** at http://resources.arcgis.com/en/help/main/10.2.

Getting ready

In this section, we will display the topology layer in ArcMap, and test different methods to fix the topology errors identified in the previous recipe.


The main steps in editing a topology are:

- 1. Open the topology in ArcMap.
- 2. Symbolize your topology by the error type.
- 3. Examine the list of errors with Error Inspector.
- 4. Use Fix Topology Error to examine errors individually.
- 5. Use predefined fixes to correct an error / manually correct an error by using ArcMap's editing tools or **Topology Edit Tool**.
- 6. Define exceptions to the rule.
- 7. Display the *dirty areas* and validate the topology.
- 8. Save the edits.

How to do it...

Follow these steps to edit LandUse Topology in ArcMap:

- Start ArcMap, and open an existing map document EditingTopology.mxd from <drive>:\PacktPublishing\Data\EditingData. Click on the Add Data button, and load LandUse_Topology from ...\Data\TOPO5000.gdb\LandUse. Select Yes in the pop-up window to add all feature classes that participate in LandUse Topology.
- 2. In the **Table Of Contents** section, drag the BuildingsR layer above the LandUse layer. Set the transparency for BuildingsR and LandUse at 60 percent.
- 3. Right-click on LandUse_Topology, and navigate to **Properties** | **Symbology**. Notice that the error features may be points, lines, or polygons depending on the error types. Inspect all other tabs to review the ranks, rules, and errors from the previous recipe, *Creating geodatabase topology*. Click on **OK** to close the window.
- 4. Start an edit session. Click on the drop-down arrow from the right-hand side of the Editor toolbar, and select Customize. Check the Topology toolbar, and click on Close. Select the Error Inspector tool from the Topology toolbar and dock the window at the bottom of the ArcMap window, as shown in the following screenshot:







Editing Data

- 5. Uncheck Visible Extent Only, select <Errors from all rules> in the Show drop-down list, and click on the Search Now button. Inspect the rules and the columns in the Error Inspector window. If we click on any of the column headings, we change the order of the errors accordingly. If we select a row, we see the selected error on the map. The Shape column tells you about the error geometry: polygon error, polyline error, or point error.
- Let's examine and correct some errors with the Fix Topology Error tool. First select <BuildingsR: Dwelling-Must Be Covered By-LandUse:Other terrains> in the Show drop-down list, and click on the Search Now button.
- 7. Select the first error, shown as Must Be Covered By | BuildingsR:Dwelling | LandUse:Other terrains | Polygon | 72 | 0 | False. Right-click on the error, and choose Zoom To. The Dwelling subtype is on the Arable parcel. This is a violation of the rule that says that the Other terrains subtype parcel must contain only the Dwelling subtype buildings. Because the orthophoto map is from 2012, and some changes could have happened, we can assume that this error could be a false error, and we will declare it as an exception to the rule. With the Fix Topology Error tool, select the error, right-click on the map, and select Mark as Exception. To see this exception, check Exceptions in the Error Inspector window. Click on Search Now to refresh the rows.
- 8. Select the next error, shown as **Must Be Covered By** | **BuildingsR:Dwelling** | **LandUse:Other terrains** | **Polygon** | **77** | **0** | **False**. Right-click on the error, and choose **Zoom To**. The dwelling is overlapping on two parcels. This is a real error, and you should correct it. How do you do it? With the **Fix Topology Error** tool, select the error, right-click on the map, and select **Select Features**.
- 9. There are three main possible solutions: delete a vertex, use **Topology Edit Tool**, or use **Reshape Edge Tool** and slightly shift the buildings.
 - 1. **First solution**: Click on **Edit Vertices** from the **Edit** toolbar. With the pointer on vertex 4, right-click on and choose **Delete Vertex**, as shown in the following screenshot:

Chapter 2



 Second solution: Click on Topology Edit Tool, and select edge (1). Select the Reshape Edge Tool option, and draw a line between points (2) and (3), as shown in the following screenshot. To unselect the edge, click on Reshape Edge Tool, and click outside the building feature.



3. **Third solution**: With the building selected, click on **Rotate Tool** from the **Editor** toolbar, press the *A* key to set the rotate angle at 4 gons. Type 4, and press the *Enter* key. Click on **Edit Vertices** from the **Edit** toolbar, and delete the cracking points that were added on both the edges of the building in the validation process.



Editing Data

As we can see, the last solution seems to be more proper for the building because the geometry of the building remains unchanged.

- 10. Unselect the feature with Clear Selected Features from the Standard toolbar. Because we edited a feature, let's see the *dirty area*. Right-click on LandUse_ Topology, and navigate to Properties | Symbology. Check the Dirty Areas option, and click on OK. You will see a small blue hatched rectangle. This means that your topology needs to be validated on this area. Select Validate Topology in Specified Area, and draw a bigger box on your dirty area. Now your area is validated, and the error has disappeared from the list.
- Let's continue to correct errors for the LandUse layer. In the Error Inspector window, select < LandUse-Must Not Have Gaps> in the Show drop-down list, and click on the Search Now button. Select the first error, right-click on the error, and choose Zoom To. The error delineates the entire area. This is a false error, which you will declare as an exception to the rule. With the Fix Topology Error tool, select the error, right-click on the map, and select Mark as Exception. Click on Search Now to refresh the rows.
- 12. Select the second error in the **Error Inspector** window, right-click on the error, and choose **Zoom To**. With **Fix Topology Error**, right-click on the map, and choose **Select Features**. There are two possible solutions: use a predefined fix or edit the vertices, which are explained in detail here:
 - First solution: With the Fix Topology Error tool, select the error, right-click on the map, and choose the predefined fix: Create Feature. You now have a new feature that fills the gap. Select both parcels and use Merge from the Editor toolbar to merge polygons (1) and (2) as shown in following screenshot:




- Second solution: Select the parcel, and click on Edit Vertices from the Edit toolbar. With the pointer on the vertex, drag the vertex from point (1) to point (2).
- 13. Use the **Validate Topology In Current Extent** tool to validate the changes you have made.
- 14. In the Error Inspector window, select < LandUse-Must Not Overlap> in the Show drop-down list, and click on the Search Now button. Select the first polygon error, right-click on the error, and choose Zoom To. With the Fix Topology Error tool, select the error, right-click on the map, and select Merge, as shown in the preceding screenshot. In the Merge window, select Built-up area (LandUse), and click on OK. Click on Search Now to refresh the rows. Correct the second error yourself using the same steps. Consider as exceptions the last four errors from the < LandUse-Must Not Overlap> list. Select all four errors at once, and right-click on and choose Mark as Exception. If you change your mind, just right-click on and choose Mark as Error.
- 15. Zoom to **Full Extent**, validate using the **Validate Topology In Current Extent** tool, and refresh the error list in the **Error Inspector** window.
- 16. Save your edits and stop the edit session. Save the map document to <drive>:\ PacktPublishing\Data\EditingData as MyEditingTopology.mxd.

You can find the results at ...\Data\EditingData\MyTopologyResults\ EditingTopology.mxd.

How it works...

The validation of spatial data and correction of the topological errors improve the quality of our data but do not increase the accuracy of our spatial data.

The small overshoot and undershoot errors can be fixed through the validation process as shown in the following screenshot:



Do not increase the value of cluster tolerance to automatically fix this kind of error in your spatial dataset.



Editing Data -

The topology validation is an iterative process. The simultaneous use of different topological rules should be performed moderately. Try to keep the number of topology rules as small as possible.

We have noticed that a single mistake in feature geometry might violate multiple rules and generate different geometry errors (for example, polygon and polyline errors at the same time). The correction of some topological errors might generate new topological errors notified by other topological rules applied to the datasets. In order to avoid the recurrent correction of the errors on the same vectors, it is recommended that you create, for example, a topology only for features from LandUse. After we have corrected all errors between features from the same feature class, we should delete the topology. After that, we can create another topology between the BuildingsR and LandUse feature classes.


Another good idea is that we should first create a topology, and after that, we should create relationships and define relationship rules between the BuildingsR and LandUse feature classes (the *Creating a relationship class* recipe of *Chapter 1*, *Designing Geodatabase*). Otherwise, we have to pay attention to those relationships while correcting the topology errors.

The **Must be larger than cluster tolerance** rule helps us to identify the small residual polygons or polylines resulted in the edit process or from different geoprocessing tasks. As a general practice, there is an order of correcting errors from a topology as follows: correct the polygon errors, correct the polyline errors, and finally correct the point errors.

There's more...

Some of the topology errors can be considered *false errors*, which means that involved features will not obey the topology rules. Most of the time, those kinds of errors have to be identified by the operator and be declared as *exceptions* to the topological rules.

In ArcCatalog, inspect the properties of WatercourseL_Topology from ...\Data\ EditingData\MyTopologyResults\TOPO5000.gdb\Hydrography. For all 23 errors, refer to the **Must not have dangle** rule that constrains the vectors from being connected to other vectors. This significant number of errors could suggest that rivers from the hydrography network are disconnected. These point errors are false. Only one error has been really identified, the rest of the errors having been declared as exceptions:



In the quality control report, we should mention the number of identified and corrected errors. It is also necessary to specify the number of exceptions to prevent the following overall assessment: *your spatial data has been created with a doubtful quality and significant corrections were applied*.

See also

 In the next chapter, we will work with different coordinate reference systems in a file geodatabase

In this chapter, we will cover the following topics:

- Understanding projections
- Projecting vector data
- Georeferencing raster data
- Setting a custom coordinate reference system

Introduction

In accordance with the international standard ISO 19111:2007, geographic information spatial referencing by coordinates, the following definitions are universally agreed upon:

- ► A **Coordinate Reference System** (**CRS**) is a coordinate system that is related to an object through a datum. For geodetic and vertical datums, the object is the Earth.
- A datum is a set of parameters that defines the position of the origin, the scale, and the orientation of a coordinate system.
- A geodetic datum describes the relationship of a 2D or 3D coordinate system to the Earth.

- A geoid is the equipotential surface of the Earth's gravity field that is everywhere perpendicular to the direction of gravity. The geoid best fits mean sea level either locally or globally. A geoid is considering the true shape of the Earth.
- A projected coordinate reference system is a coordinate reference system derived from a two-dimensional geodetic coordinate reference system by applying a map projection.
- A vertical coordinate reference system is a one-dimensional coordinate reference system that is based on a vertical datum. A vertical datum describes the relation of the gravity-related heights to the Earth. A vertical datum is related to a geoid.

A geocentric coordinate reference system is a geodetic coordinate reference system that has the origin in the center of the mass of the Earth (geocenter) and usually is expressed in rectangular Cartesian coordinates (X, Y, Z).

An ellipsoid models the size and shape of the Earth. The ellipsoid (ellipsoid of reference) is formed by rotating the meridian ellipse about its minor axis (oblate ellipsoid). The ellipsoid generated by rotating the meridian ellipse about its major axis is a prolate ellipsoid. You need at least two parameters to define the size and shape of an ellipsoid (one parameter must be the semi-axis).

Generally speaking, the difference between the major and minor axes is small, and the shape is close to a sphere. Because it approximates the shape of a sphere, we call it a spheroid. For example, the **Geodetic Reference System 1980** (**GRS80**) has the semi-major axis length of 6,378,137 meters and the semi-minor axis length of 6,356,752.31414 meters. The terms ellipsoid and spheroid will be used interchangeably.


An ellipsoidal coordinate system works with geodetic latitude (B or ϕ), geodetic longitude (L or λ), and ellipsoidal height (h).

When the Earth is considered a sphere, we use a spherical coordinate system with its origin in the center of the sphere (spherical latitude ϕ and spherical longitude λ).

In ArcGIS, you will find both the ellipsoidal and spherical coordinate system in the geographic coordinate systems folder. In the ArcGIS context, a geographic coordinate system has three components: angular units, prime meridian, and datum (spheroid).

- 72

When you are working with **Vertical Coordinate Systems**, please take into account the difference between the ellipsoidal and gravity-related heights. Ellipsoidal heights (h) use the ellipsoid as the reference surface and represent the vertical component a of 3D ellipsoidal coordinate system. Gravity-related heights (H) use as reference surface the geoid that is the component of the one-dimensional vertical coordinate system. The relationship between the ellipsoid, geoid, and topographic surfaces is as shown in the following screenshot:



- For further research, please refer to the Information and Service System for European Coordinate Reference Systems project at http://www.crs-geo.eu
- ► For theoretical aspects about geodetic datums, please refer to Geodesy, 2nd Edition, Wofgang Torge, Walter de Gruyter, 1991
- For more information about the European Vertical Reference System (EVRS2007) datum, please visit the Federal Agency for Cartography and Geodesy (BKG) at http://www.bkg.bund.de/evrs
- To see the global geoid model created by the ESA's gravity mission called GOCE, please visit the European Space Agency (ESA) at http://www.esa.int/Our_Activities/Observing_ the_Earth/GOCE/Earth_s_gravity_revealed_in_ unprecedented detail

As a final remark, please be aware about the difference between the transformation and conversion processes. A transformation involves a change of datum (for example, from GRS80 to Krassowsky 1940), and a conversion does not involve a change of datum (for example, geographic coordinates ϕ and λ to projected coordinates *N* and *E*).

73 –

Understanding projections

In this recipe, you will self-study different map projections in three types of projections: Azimuthal, Cylindrical, and Conical.

For theory regarding the map projections, please refer to:

- Datums and Map Projections 2nd Edition Jonathan Iliffe and Roger Lott, Whittles Publishing, 2012
- Understanding Map Projections; Melita Kennedy and Steve Kopp, Environmental Systems Research Institute, Inc., 2000

In the map document CRS.mxd, there are marked with a red rectangle the main map projections for Europe as recommended by **INSPIRE Directive** in the *Data Specification on Coordinate Reference Systems* document.

Getting ready

While you inspect every map projection, try to identify the following:

- What is the projection type?
- What are the parameters necessary to define the projection (for example, latitude and longitude of the origin, first/second standard parallel, scaling factor, and false easting and northing for all coordinates)?
- ▶ What ellipsoid is used (from datum)?
- What features preserve (for example, distances: equidistant projection; areas: equal area projection; angles: conformal projection)?


How to do it...

Follow these steps to study what Europe looks like in different map projections using ArcMap:

 Start ArcMap, and open the existing map document CRS.mxd from: <drive>:\PacktPublishing\Data\CRS, as shown in the following screenshot:

- 74

Chapter 3



2. The Table Of Contents section contains ten Data Frames in Layout View with different Coordinate Systems. Every data frame contains the same NUTS_RG_03M_2010 layer from the NUTS_2010_03M.mdb personal geodatabase. In Layout View, you can see all data frames at once. Data View allows you to view only one data frame at a time. You can switch between Data View and Layout View if you click on the small buttons from the lower-left part of the map display window (3). Keep Layout View activated. In Layout View, use the Zoom In (1), Zoom Out, and Pan (2) tools from the Layout toolbar to study the aspect of the graticules for every data frame's projection.

75 —


Working with CRS _____

3. Let's check the first data frame's coordinate system. Right-click on the first data frame **ETRS89_EPSG::4258**, and navigate to **Properties** | **Coordinate System**, as shown in the following screenshot:

Data Frame Properties	X
Annotation Groups Extent Indicators Frame Size and Position General Data Frame Coordinate System Illumination Grids	Product Library Feature Cache
🚡 🕶 🛛 Type here to search 🔹 🧟 🛞 🖉 🕶	*
 Favorites Geographic Coordinate Systems Africa Antarctica Asia Asia Atlantic Ocean Australia and New Zealand Caribbean County Systems 	-
Current <u>coordinate system</u> : GCS_ETRS_1989 WKID: 4258 Authority: EPSG	*
Angular Unit: Degree (0.0174532925199433) Prime Meridian: Greenwich (0.0) Datum: D_ETRS_1989 Spheroid: GRS_1980 Semimajor Axis: 6378137.0 Semiminor Axis: 6356752.314140356 Inverse Flattening: 298.257222101	~
Transformations	
OK Cancel	Apply

- 76 -

4. Notice that the coordinate system is set to the GCS_ETRS_1989 coordinate system with the EPSG geodetic code 4258. This is a 2D geographic coordinate system. To read more about it, please check the website http://www.epsg-registry.org. EPSG is the acronym for European Petroleum Survey Group. As shown in the following screenshot, select retrieve by code (1), type 4258 (2), and click on Retrieve (3) to find the ETRS89 coordinate reference system characteristics, as shown in the following screenshot:



77 –

- 5. To see more details and the geodetic parameters, click on view (4).
- 6. Let's inspect the second data frame: ETRS89_LAEA_EPSG::3035. To activate the data frame, press the *Alt* key, and select the data frame in the Table Of Contents (TOC) section. The name of the activated data frame is indicated in bold letters in TOC. You can activate a data frame by right-clicking on ETRS89_LAEA_EPSG::3035 and selecting Activate. The activated data frame will have a gray dashed border in the map display window.
- 7. It is a **Projected Coordinate System** named **Lambert Azimuthal Equal Area**. This projection is recommended by the INSPIRE Directive in the *Data Specification on Coordinate Reference Systems* document on *page 7*.
- To read this material, please visit the website http://inspire.ec.europa.eu. Navigate to Data Specifications | Technical Guidelines Annex I | INSPIRE Data Specification on Coordinate Reference Systems –Technical Guidelines 3.2 17.04. 2014.
- 9. Repeat step 5 to see more details on http://www.epsg-registry.org using the code **3035**.
- 10. Continue to inspect every data frame from CRS.mxd and compare the projections (for example, graticules and distortions of the feature shapes).

How it works...

The NUTS_RG_03M_2010 layer is projected on the fly in accordance with the **Coordinate System** option of the **Data Frame** section. This mean that layer projection is only temporarily changed inside the data frame. The on-the-fly transformation does not affect the original coordinate values in the feature class.

See also

If you want to change the graticule intervals in Layout View, please refer to Chapter 7, Exporting Your Maps. In the next Projecting vector data recipe, you will transform a geographic coordinate system into a projected coordinate system for a feature class in a file geodatabase.

- 78

Projecting vector data

In the previous recipe, you saw the same NUTS_RG_03M_2010 feature class that has the ETRS89-GRS80 geographic coordinate system in nine data frames that have different projected coordinate systems. The projection of the feature class was made on the fly by ArcMap based on every data frame's projected coordinate system.

To permanently transform the coordinate reference system of a feature class, use the **Project** tool from **ArcToolbox**. This will create a new feature class with the new coordinates for the features. ArcGIS offers multiple versions of a transformation between different datums. It's important to choose the optimal transformation because it will affect the coordinates' accuracy.


At <ARCGISHOME>: \Desktop10.2 \Documentation, you will find a PDF file called geographic_transformations.pdf that lists all supported datum transformations and the areas for which they are suited.



For theory and worked examples about coordinate system transformations, please refer to Datums and Map Projections 2nd Edition Jonathan Iliffe and Roger Lott, Whittles Publishing, 2012, chapter Map Projection, p.39-89; Appendix E.3.3, Subsets of the seven-parameter geocentric transformation, p.196-199

Getting ready


Let's follow the steps to transform the AdministrativeUnits standalone feature class from the geographic coordinate system (GCS) ETRS_1989 to the projected coordinate system Pulkovo_1942_Adj_58_Stereo_70 using the predefined transformation from ArcGIS:





How to do it...

Follow these steps to transform the coordinates for a feature class in the ArcCatalog application:



- Start ArcCatalog. In the Catalog Tree section, go to <drive>:\ PacktPublishing\Data\CRS and select Topo5k.gdb.
- The file geodatabase has an empty feature dataset. Right-click on the Boundaries feature dataset, and navigate to Properties | XY Coordinate System. To go to the current coordinate system, navigate to the Projected Coordinate System | National Grids | Europe projected coordinate system named Pulkovo_1942_Adj_58_Stereo 70 with the EPSG code 3844.
- 3. Let's add some data. Search on Google for Eurostat website with following key words: eurostat statistical units. You should find the following link Administrative units and Statistical units Eurostat: http://ec.europa.eu/eurostat/web/ gisco/geodata/reference-data/administrative-units-statisticalunits.
- 4. Read carefully the **Copyright** notice, and download the NUTS 2010 dataset as a personal geodatabase: NUTS_2010_3M.zip. Unzip the archive file in <drive>:\ PacktPublishing\Data\CRC\NUTS2010. You now have a personal geodatabase with the administrative units for Europe at 1:3,000,000 scale.



- NUTS_2010_03M.mdb
 CNTR_AT
 NUTS_AT_2010
 NUTS_BN_03M_2010
 NUTS_JOIN_LI_2010
 NUTS_RG_03M_2010
 NUTS_RG_BN_03M_2010
 NUTS_SEPA_LI_2010
 NUTS_SEPA_LI_2010
 GopoSk.gdb
 Boundaries
 AdministrativeUnits
- 5. Import the NUTS_RG_03M_2010 feature class into Topo5k.gdb, as a standalone feature class:

6. In the Catalog Tree section, right-click on Topo5k.gdb and navigate to Import | Feature Class (single). Specify Input Feature, Output Location, and Output Feature Class (as AdministrativeUnits), and click on OK, as shown in the following screenshot:

Feature Class to Feature Class		
Input Features		
ookbook\Data\CRS\WUTS_2010_03M.mdb\WUTS_RG_03M_2010	2	
Output Location		
\PACKT_PUBLISING\++ArcGIS Cookbook\Data\CRS\Topo5k.gdb	2	
Output Feature Class		
AdministrativeUnits		
Expression (optional)		
	SQL	
Field Map (optional)		
STAT_LEVL_CODE (Long)		
	_	
	×	
		Ŧ
OK Cancel Environments Show	Help >>	



- Right-click on the AdministrativeUnits feature class, and navigate to Properties | XY Coordinate System. To go back to the current coordinate system, navigate to the Geographic Coordinate System | Europe GCS named ETRS 1989 with the EPSG code 4258.
- 8. If you want to move the **AdministrativeUnits** standalone feature class in the Boundaries feature dataset, you simply select the feature class and drag and drop it into the feature dataset. You will not succeed because the feature datasets have a different spatial reference. You will receive the following error message: **The spatial reference does not match**.
- 9. Let's use the **Project** tool to transform the **AdministrativeUnits** standalone feature class from the geographic coordinate system in a projected coordinate system. Open **ArcToolbox**, and navigate to **Data Management Tools** | **Projections and Transformation**. Double-click on the **Project** tool to open the dialog box shown in the following screenshot:

S Project	x
Input Dataset or Feature Class (1)	
,++ArcGIS Cookbook\Data\CRS\Topo5k.gdb\AdministrativeUnits	
Input Coordinate System (optional)	
GCS_ETRS_1989	
Output Dataset or Feature Class (2)	E
>k\Data\CRS\Topo5k.gdb\Boundaries\EuropeAdministrativeUnits	
Output Coordinate System	
Pulkovo_1942_Adj_58_Stereo_70	
Geographic Transformation (optional)	
(3)	
Pulkovo_1942_Adj_1958_To_ETRS_1989_4	Ŧ
(4) OK Cancel Environments Show Help >>	

- 10. Specify the Input Dataset or Feature Class step (1) of Topo5k.gdb\ AdministrativeUnits. Specify the Output Dataset or Feature Class (step 2) of Topo5k.gdb\Boundaries, and type the name of the feature class as EuropeAdministrativeUnits.
- 11. The **Output Coordinate System** was automatically added because the newly created feature class will inherit the coordinate system of the feature dataset of Boundaries.
- **12.** At step (**3**) **Geographic Transformation**, choose the Pulkovo_1942_Adj_1958_ To_ETRS_1989_4 geographic transformation. Click on **OK**.
- 13. This is the best transformation for your feature class, also take into account the input and output CRSs and the covered area. To choose a proper datum transformation please go through the following steps:
 - 1. Open the geographic_transformations.pdf document from <ARCGISHOME>:\Desktop10.2\Documentation and go to page 67 to read the following row: Pulkovo_1942_Adj_1958_To_ETRS_1989_4 15994 CF 2.3287 -147.0425 -92.0802 0.3092483 -0.32482185 -0.49729934 5.68906266. Read the details from page 75 regarding the geographic transformation method called CF or Coordinate_Frame that is a seven-parameter geocentric transformation.
 - 2. Check the parameters of the transformation **EPSG::15994** at http://www.epsg-registry.org. Using the **EPSG::15994** datum transformation the accuracy of the horizontal position will range from 1.5 meters to 3 meters.
- 14. Use ArcMap to see the EuropeAdministrativeUnits feature class.

There's more...

Let's define two custom geographic transformations between the ETRS89 datum with the ellipsoid GRS 1980 (EPSG: 4258) and the Pulkovo 1942 datum with the ellipsoid Krassowsky 1980 (EPSG: 4179) using a seven-parameter transformation.

Follow these steps to define two custom geographic transformations in ArcCatalog using **ArcToolbox**:

1. Open ArcToolbox, and navigate to Data Management Tools | Projections and Transformation. Double-click on the Create Custom Geographic Transformation tool to open the dialog box, as shown in the following screeenshot:

Create Custom Geographic Tra	nsformation	
Geographic Transformation Name	(4)	A
Helmert_7_GRS80_To_Krasovsky	1.7	
Input Geographic Coordinate Syste		
GCS_ETRS_1989	(2)	
Output Geographic Coordinate Sys	tem	
GCS_Pulkovo_1942_Adj_1958	(3)	
Custom Geographic Transformation		
Method		
COORDINATE_FRAME	(4)	•
Parameters		
Parameters	(5)	
Name	Value (5)	<u>^</u>
X Axis Translation (meters)	-2.3283	=
Y Axis Translation (meters)	147.0416	
Z Axis Translation (meters)	92.0802	
X Axis Rotation (seconds)	-0.30924979	-
Y Axis Rotation (seconds)	0.32482188	=
Z Axis Rotation (seconds)	0.49730012	-
Scale Difference (ppm)	-5.68907711	-
		•
OK Cancel	Environments	Show Help >>

- 2. For Geographic Transformation Name, type Helmert_7_GRS80_To_ Krassowsky1940 (step 1) to define the name of your transformation.
- For Input Geographic Coordinate System (step 2), select the icon from the right-hand side to open the Spatial Reference Properties dialog. From the Geographic Coordinate Systems folder, navigate to Europe | ETRS 1989. Select the Z Coordinate System tab, and navigate to Vertical Coordinate Systems | Europe | ETRS 1989. Click on OK.




- For Output Geographic Coordinate System (step 2), select icon from the right-hand side to open the Spatial Reference Properties dialog. From the Geographic Coordinate Systems folder, navigate to Europe | Pulkovo 1942 Adj 1958. Select the Z Coordinate System tab, and navigate to Vertical Coordinate Systems | Europe | Constanta. Click on OK.
- 5. In the Custom Geographic Transformation section, select as Method the COORDINATE_FRAME option. You will have to specify all seven parameters (step 4), as shown the preceding screenshot. Those parameters are from the official site of the National Agency of Cadastre and Land Registration from Romania: www.ancpi.ro. Click on OK.
- 6. Open again the **Create Custom Geographic Transformation** tool to create the second transformation named Helmert_7_ Krassowsky1940_To_ GRS80, as shown in the following screenshot:


Geographic Transformation Name	A
Helmert_7_Krasovsky1940_To_GRS8	80
Input Geographic Coordinate System	
GCS_Pulkovo_1942_Adj_1958	
Output Geographic Coordinate System	m
GCS_ETRS_1989	F
Custom Geographic Transformation	
Method	
COORDINATE_FRAME	▼
Parameters	
Name Va	alue
X Axis Translation (meters) 2.	3287
Y Axis Translation (meters) -1	47.0425
Z Axis Translation (meters) -9	2.0802 *
X Axis Rotation (seconds) 0.	30924830
Y Axis Rotation (seconds) -0	.32482185
	.49729934
	6890626 👻
•	•
	-
OK Cancel I	Environments Show Help >>



7. You can see the custom geographic transformations in the .gtf format at C:\ Users\<user>\AppData\Roaming\ESRI\Desktop10.2\ArcToolbox\ CustomTransformations, as shown in the following screenshot:



Let's follow the next image to project once again the AdministrativeUnits standalone feature class from GCS_ETRS_1989 to Pulkovo_1942_Adj_58_Stereo_70 using your custom transformation Helmert_7_GRS80_To_Krassowsky1940:



You will transform your feature class using the first two steps:

- 1. Geographic transformation or change of datum: Open ArcToolbox, navigate to Data Management Tools | Projections and Transformation, and double-click on the Project tool. Set the following parameters and click on OK:
 - □ Input Dataset or Feature Class: Topo5k.gdb\ AdministrativeUnits.
 - Output Dataset or Feature Class: Topo5k.gdb\ Krassowsky_Europe.
 - Output Coordinate System: Geographic Coordinate System | Europe: Pulkovo 1942 Adj 1958.
- 2. Map the projection or coordinate conversion from geographic coordinates to **Cartesian coordinates**: To add your standalone feature class in the projected coordinate system of the **Boundaries** feature dataset, use the **Project** tool again, and set the **conversion** parameters, as shown in the following screenshot:

Project	х
Input Dataset or Feature Class	
-ArcGIS Cookbook\Data\CRS\Topo5k.gdb\Krassowsky_Europe	
Input Coordinate System (optional)	<u> </u>
GCS_Pulkovo_1942_Adj_1958	
Output Dataset or Feature Class	
kbook\Data\CRS\Topo5k.gdb\Boundaries\MyProjectedEurope	
Output Coordinate System	
Pulkovo_1942_Adj_58_Stereo_70	
Geographic Transformation (optional)	
New Import Clear	
OK Cancel Environments Show Help >	·>

3. For **Output Coordinate System**, open the **Spatial Reference System** dialog. Click on the small globe on the right-hand side and navigate to **Add Coordinate System** | **Import** to go through the coordinate system from the Boundaries feature dataset. Click on **Add** and on **OK** to return to the **Project** window. Click on **OK**.




4. Use ArcMap to see the EuropeAdministrativeUnits option and MyProjected_ Europe feature classes. Inspect the two layers with the Edit Vertices (start the Edit session) and Sketch Properties tools to see whether there are any differences in the X and Y coordinates of feature vertices. If the transformation and conversion succeed, there will be no difference.

You can find the results of this section at <drive>:\PacktPublishing\Data\CRS\ MyCRSResults.

Georeferencing raster data

According to the online ESRI GIS Dictionary, the georeferencing process converts the coordinates of a raster to a known coordinate system in order to be viewed, queried, and analyzed with other spatial datasets you might have. The raster's Cartesian coordinate system is considered as a source (arbitrary) system The known or reference Cartesian coordinate system is considered as a destination (fixed) system.

In this recipe, you will follow the general concepts from the following diagram:



For theory and worked examples about coordinate transformations in two dimensions and least squares estimation, please refer to:



- Principles of Geospatial Surveying, Artur L. Allan, Whittles Publishing, 2007; chapter Coordinate Transformations, p.41-58 and chapter Least Squares Estimation, p.88-115
- Observations and Least Squares, Eduard M. Mikhail, IEP-A Dun-Donnelley Publisher, 1976; subchapter Coordinate transformations, p.184-212



Getting ready

You will georeference a raster in the TIF format that is a scanned topographic map corresponding to scale 1:5,000. The raster will represent the source coordinate system (image system).

As a reference layer, you will have a vector dataset in the dxf format (CAD data file format) that contains the grid for 1:5,000 scale maps in oblique stereographic projection with the EPSG code 3844 and the name Pulkovo 1942(58) / Stereo70. The reference layer will represent the target coordinate system (fixed).

You will use the affine transformation method or six-parameter transformation. The affine method assumes the following adjustments: translations on *x* and *y*, scale changes on *x* and *y*, and rotation on *x* and *y* (the axes are not orthogonal). The following equations express the affine transformation in 2D space:

XT = AxS + ByS + CYT = DxS + EyS + F

A, *B*, *C*, *D*, *E*, and *F* are the parameters of the transformation, *x*S and *y*S are the source coordinates (image system), and *XT* and *YT* are the target coordinates (map reference system). To estimate the six parameters using the least squares method, you need at least four points of known coordinates in both coordinate systems (source and target).

After you specify at least four links, ArcGIS will calculate the residuals on X and Y as the difference between the calculated map coordinates and the known map coordinates. The resultant Residuals = SQRT (Residual_X2 + Residual_Y2).RMS Error represents the root mean square error of an observed point. $RMSE = \pm SQRT(Sum(Residual_X2 + Residual_Y2)/number of equations-number of parameters)$


You should pay attention to the RMSE values. Usually, the values should not be greater than 0.5 pixels in dimensions. After the affine transformation (scale changes on *x* and *y*), you will have a pixel value of around 0.4 m. Trying to obtain a RMS value of 0.2 m in this case is not quite relevant for the scanned map at the scale 1:5,000.

Taking into account the classical theory of cartography, 1 mm on the map represents 5 m on the ground. The planimetric precision for a map should be between 0.1 mm and 0.3 mm.

Following this idea, let's propose for RMSE a value equal or less than 0.5 m corresponding to 0.1 mm planimetric precision on a map at the scale 1:5,000.

How to do it...

Follow these steps to georeference a scanned map (raster) in ArcMap using the coordinates from the following screenshot:




- 1. Start **ArcMap**, and open an existing map document **Georeferencing.mxd** from <drive>:\PacktPublishing\Data\CRS.
- 2. From the **Bookmarks** menu, select **Raster**. Notice the two **Overview** windows that will help you to see the full extent of raster and the control layer in .dxf format. If necessary, rearrange the windows on **Data View**.
- 3. From the **Customize** menu, navigate to **Toolbars** | **Georeferencing**. On the toolbar, choose **L35_111_Db_2III.tif** as the georeferencing layer.
- 4. Click on the View Link Table button, and uncheck Auto Adjust in Link Table.
- 5. In the next steps, you will add four links between the source points and the destination points by selecting the Add Control Points button from the Georeferencing toolbar. The green pointer indicates where the source point is, and the red pointer indicates where it should be.



91 -

- 6. From the **Bookmarks** menu, select **RasterNW**. In the **Snapping** toolbar, select **Vertex** to snap to the vertices of lines from the control layer.
- 7. Click on in the first corner of the raster to add the first source point (**Source 1**). Go to the reference layer using the bookmark **Grid 1:5000**. Click on Point 1 NW (**Destination 1**) to add the corresponding destination point using the following screenshot as a guide:



8. Use the bookmarks **RasterNE**, **RasterSE**, and **RasterSW** to repeat step 7 for the next three points. To line up the raster to the reference layer, click **Auto Adjust**, and select the **Transformation: 1st Order Polynomial (Affine)** method in **Link Table**. You should obtain similar values to the ones shown in the following screenshot:

Link									1 ×
🖆 🖬 📲 🗚 👘				Total RMS Error: Forw		Forward:0.465705			
	Link	X Source	Y Source	Х Мар	Ү Мар	Residual_x	Residual_y	Residual	
V	1	0.017848	25.878466	534603.352718	368141.692128	-0.378158	0.272382	0.466042	
1	2	27.625635	26.038822	537075.006921	368155.612601	0.377978	-0.272253	0.465821	
V	3	27.782587	0.158062	537088.492689	365840.754854	-0.377611	0.271988	0.465368	
V	4	0.147867	0.009848	534615.939427	365826.831788	0.37779	-0.272118	0.465589	
Auto Adjust				Transformation:	1st Order Polynomial (Affine)			•	
Degrees Minutes Seconds F			Forward Residual Unit : Unknown						

- 9. Notice the estimated resultant residual values and RMS Error. If you make a mistake while adding links, select the wrong link by clicking on the row and click on the **Delete Link** tool or press the *Delete* key. Add the link again by repeating step 6. If you have not obtained an RMSE equal to or less than 0.5 meter, you should delete the link with larger residual errors and add it again.
- 10. Save the links to a text file using the **Save** tool from **Link Table**. Save them in <drive>:\PacktPublishing\Data\CRS\MyGeoref as L35_111_DB_2III_ EPSG3844.txt. You can see the file using any text editor (for example, WordPad).
- 11. You can remove all points from the **Link Table** section with the **Delete Link** tool and restore them with the backup file you just created using the **Load** tool.

Let's go to the last step of the georeferencing process:

- 12. On the **Georeferencing** toolbar, select the **Georeferencing** menu, and choose **Rectify** to save the georeferencing adjustments of the raster.
- 13. Accept the default values for **Cell size**, **Resample Type**, and **Format**. For **Output Location** go to <drive>:\PacktPublishing\Data\CRS and select the **MyGeoref** workspace (folder). For **Name**, type L35_111_Db_21II. Click on **Save**.
- 14. Remove the control points from **Link Table**, and close the window. Add the georeferenced raster using the **Add Data** button from the **Standard** toolbar.
- 15. In the Table Of Contents section, right-click on the L35_111_Db_2III raster, and select Properties. Select the Source tab, and examine the Spatial Reference section. Spatial Reference is Pulkovo_1942_Adj_58_Stereo_70. The spatial reference was automatically inherited by the newly created raster from the Data Frame coordinate system. To check the coordinate system of the data frame, navigate to View | Data Frame Properties | Coordinate System. Click on OK.
- 16. Save the map document at <drive>:\PacktPublishing\Data\CRC as MyGeoreferencing.mxd.

How it works...

You have georeferenced a raster using a .dxf file as the reference layer. You can add links using the **Insert Links** button from the **Link Table** window. You can also modify the existing coordinate values directly by editing the fields of the links. The **Rectify** command has created a new raster and a world-file in a separate ASCII file with the same name as that of the raster file, with a "w" attached. Open Windows Explorer, go to <drive>:\PacktPublishing\ Data\CRS\MyGeoref, and open the file L35_111_DB_2III.tfw with any text editor to see the content. This file contains the six parameters of the affine transformation associated to the new raster.



For more details regarding the world-file, please refer to http://resources.arcgis.com/en/help/ main/10.2, and navigate to **Geodata** | **Data types** | **Rasters and images online** in ArcGIS Help (10.2).

At step 10, you saved the links in the L35_111_DB_2III_EPSG3844.txt file. If you open this file, you see there is no information about the spatial reference or RMS value. It is recommended that you save the RMS value, because this information should be specified in the Quality and Validity section from Metadata. According to the Infrastructure for Spatial Information in the European Community (INSPIRE) directive, metadata is an important component of an infrastructure for spatial information. **Metadata** means information describing spatial datasets and spatial data services (INSPIRE Directive 2007/2/EC, Article 3).



For further research, please refer to the INSPIRE Directive 2007/2/EC and for elements of metadata, please refer to the adoption/metadata section from: *http://inspire.ec.europa.eu*

Setting a custom coordinate reference system

In this recipe, you will define a custom projected coordinate reference system. Your CRS will have the following parameters:


- A geodetic datum:
 - The reference ellipsoid is at Krassowsky 1940 (semi-major axis: 6378245.000 m and inverse flattening: 298.3)
 - The fundamental astronomic point at the Pulkovo observatory with the latitude 59°46'18.550"N and longitude 30°19'42.090"E
 - Derime Meridian at Greenwich.
- Projection: A conformal azimuthal perspective projection (stereographic), it is also an oblique stereographic projection on a secant projection plane, with the following parameters:
 - Latitude and longitude of origin (projection pole = center of projection) are φ0 = 460 N and λ0 = 250 E
 - Scale factor (rectangular coordinates from the tangent plane to the secant plane) is 0.999,750,000
 - False easting = 500,000 and false northing = 500,000 (the origin of the rectangular coordinate system is the projected image of the projection pole)



You will consider that ellipsoidal coordinates are transformed first (conformal transformation) into spherical coordinates (considering radius of sphere equal to the mean radius of the ellipsoid at projection origin: $\lambda 0 = 250$), and then coordinates are projected onto the projection plane.

Getting ready

To double-check all the parameters, please go to http://epsg.io, type 3844, and click on **Search**. You will find the following details:




How to do it...

Let's define a custom projected coordinate reference system in ArcCatalog using the parameters from epsg.io:

1. Start **ArcCatalog**. In the **Catalog Tree** section, navigate to <drive>:\ PacktPublishing\Data\CRS\Topo5k.gdb.

94

 Right-click on the Boundaries feature dataset, and navigate to Properties | XY Coordinate System. Click on the small, gray globe icon, and navigate to New | Projected Coordinate System, as shown in the following screenshot:



3. In the **New Projected Coordinate System** window (step **1**), for **Name**, type ObliqueStereographic70.

95 —

Working with CRS _____

At step (2), you will define the project method. Navigate to Projection | Name, select Double_Stereographic. Type the parameters of projection at step (3). For Linear Unit, select Meter , and the value 1 for Meters per unit. The following screenshot guides you through these steps diagrammatically:

v Projected Coordinat	e System			х
ieneral				
Name:	Obliqu	eStereographic70	(1)]
Projection				
Name:	Double	e_Stereographic	(2) -]
Parameter		Value	(3) 🔺	
False Easting		500000.00000000000	000000	
False_Northing		500000.00000000000	000000	
Central_Meridian		25.0000000000000000	0000	
Scale_Factor		0.999750		
Latitude_Of_Origin		46.00000000000000000		
Linear Unit				ן ה
Linear Unit Name:	Meter		•]
	Meter]
Name:	1		(4)	
Name: Meters per unit: Geographic Coordinate Name: GCS_Pulkovo Angular Unit: Degree Prime Meridian: Gree Datum: D_Pulkovo_ Spheroid: Krasovsk Semimajor Axis: 6 Semiminor Axis: 6 Inverse Flattening	1 	532925199433) 0) _1958	(4) Change	
Name: Meters per unit: Geographic Coordinate Name: GCS_Pulkovo Angular Unit: Degree Prime Meridian: Gree Datum: D_Pulkovo_ Spheroid: Krasovsk Semimajor Axis: 6 Semiminor Axis: 6	1 	532925199433) 0) _1958		


 At step (4) you will choose the datum of projection. Select Change to open the Geographic Coordinate System window. Navigate to Geographic Coordinate Systems | Europe, and select Pulkovo 1942 Adj 1958. Click on OK.



- 6. In **Feature Dataset Properties**, there is a new folder, **Custom**, that contains your custom projection. Select the custom projection, and right-click to select **Add To Favorites**.
- 7. Close the window without applying the new projection. Click on Cancel.
- 8. You can see and use the projection from the **Favorites** folder in the **ArcCatalog**, **ArcMap**, or **ArcToolbox** context.

How it works...


When you created the custom projected coordinate reference system, it was created as a virtual **Custom** folder that stores the projection file (.prj). You have chosen to export it to the **Favorites** folder in order to have access at the file content. You can find the newly created file at C:\Users\<user>\AppData\Roaming\ESRI\Desktop10.2\ArcMap\Coordinate Systems, as shown in the following screenshot:



97 —

Working with CRS

The .prj file is a text file that stores the parameters of the geodetic coordinate reference system (for example, datum, prime meridian, and scale factor) and the vertical reference system. To see the content of the file in Windows Explorer, right-click ObliqueStereographic70.prj, and choose WordPad to open the file:



You can find also the ObliqueStereographic70.prj file at <drive>:\ PacktPublishing\Data\CRS\MyCRSResults.

See also

If you want to define your own coordinate reference system, consult carefully the following resources:

- The Esri documents that are available are as follows:
 - geographic_coordinate_systems.pdf
 - projected_coordinate_systems.pdf
 - geographic_transformations.pdf
- INSPIRE specifications on coordinate reference systems are available at http://inspire.ec.europa.eu.
- > Databases with coordinate reference systems and transformations are available at:
 - http://www.epsg-registry.org
 - http://spatialreference.org
 - http://epsg.io



In this chapter, we will cover the following topics:

- Spatial joining features
- Using spatial adjustment
- Using common tools
- Creating models

Introduction

According to the online **ESRI GIS Dictionary**, a **geoprocess** is a GIS operation used to manipulate data. A geoprocess implies creating new data based on existing data. In general, this happens in the following circumstances:

- When data is copied, imported, or added from one source to another source (for example, a geodatabase)
- > During data conversion (for example, loading data in a feature class from a CAD file)
- When analyzing data, that is, combining features or/and attributes from one or more dataset to create a new dataset

This chapter has the following scenarios:

- Counseling the local public administration
- Promoting alternative methods of transportation cycling
- Initiating a pilot project named VeloGIS

The goal is to analyze the possibility of creating a cycling infrastructure in our city. We already have a file geodatabase model named VeloGIS.gdb, and we received five CAD datasets from two departments of municipality.

Spatial joining features

The **Spatial Join** tool is an overlay geoprocessing tool. This tool will join the attributes coming from a feature class to another feature class, based on their spatial relationship. The new feature class will have the geometry of the target feature class and the attribute fields of both the input feature classes. The spatial join is a classical solution when you want to extract data from CAD files.

Getting ready

In this recipe, you will add data from the .dxf source datasets to an existing geodatabase named VeloGIS.gdb. Your geodatabase contains one feature dataset named Planimetry and five empty feature classes: Buildings1, Parcels1, RoadCenterLine, SideWalk, and Streets1.

There are five CAD files: Buildings.dxf, Parcels.dxf, RoadCenterLine.dxf, SideWalk.dxf, and Streets.dxf.

How to do it...

Follow these steps to populate your VeloGIS geodatabase with features from the .dxf files, using ArcCatalog:

- Start ArcCatalog. Navigate to <drive>:\PacktPublishing\Data\ Geoprocessing, and select the DXF folder to see the five .dxf files: Buildings, Parcels, RoadCenterLine, SideWalk, and Streets.
- 2. Expand the Buildings CAD feature dataset, and preview the features from the CAD Polygon feature class. Right-click on the feature dataset, and navigate to Properties | General. The Coordinate Systems field is unspecified. Click on the Edit button, navigate to Add Coordinate System | Import, and then go to <drive>:\PacktPublishing\Data\Geoprocessing\VeloGIS.gdb. Select the Planimetry feature dataset, and navigate to the Add | OK buttons to return to CAD Feature Dataset Properties. Explore by yourself the contents of the Coordinates and the Details tab. Click on OK to close the dialog. Repeat the step for Parcels, SideWalk, and Streets.

- 3. Go to <drive>:\PacktPublishing\Data\Geoprocessing\ VeloGIS.gdb\ Planimetry. Right-click on the Buildings1 feature class and navigate to Load | Load Data. Set the following parameters from the panels:
 - Set the Input data parameter as the ...\Data\Geoprocessing\DXF\ Buildings.dxf: Polygon feature class; click on Add
 - Check I do not want to load all features into a subtype
 - **Target Field** (destination) and **Matching Source Field** (source):

```
HCDC [int] = <None>
Structure [string] = <None>
State [string] = <None>
```

- Check Load all of the source data
- 4. Click on **Finish** to load the features. Preview the Buildings1 feature class in ArcCatalog to check if the polygon streets were loaded.
- 5. Repeat step 3 to populate the Parcels1, SideWalk1, and Streets1 feature classes with features.

Follow these steps to export the specific attributes as a standalone point feature class from the Annotation CAD feature class in ArcCatalog.

- 6. Let's return to ... \Data\Geoprocessing\DXF\Buildings.dxf. Expand the Buildings CAD feature dataset. Right-click on the Annotation feature class, and navigate to Export | To Geodatabase (single).
- 7. For Output Location, select VeloGIS.gdb, and click on Add. For Output Feature Class, type DestinationBuilding. For Expression (optional), select the SQL icon from the right-hand side. In the Query Builder dialog, build the following expression: "Layer" = '0'. How do you do that? Double-click on "Layer" and select the Equal button. Click on the Get Unique Values button, and double-click on the 0 value to add it into the expression. Click on OK to return to the Feature Class to Feature Class dialog.
- 8. In **Field Map (optional)**, delete all the fields except **Text (Text)**. The **Text** field contains the values for the **Destination** field in the Building feature class. Click on **OK**.
- 9. Right-click on the Annotation feature class once again, and navigate to **Export** | **To Geodatabase** (single).
- 10. For Output Location, select VeloGIS.gdb, and click on Add. For Output Feature Class, type StructureBuilding. For Expression (optional), select the SQL icon from the right-hand side. In the Query Builder dialog, build the following expression: "Layer" = 'Material and State' AND "Height" = 1.5. Click on OK to return to the Feature Class to Feature Class dialog. In Field Map (optional), delete all the fields except Text (Text). Click on OK.



11. Right-click on the Annotation feature class, and navigate to Export | To Geodatabase (single). For Output Location, select VeloGIS.gdb, and click on Add. For Output Feature Class, type StateBuilding. For Expression (optional), build the following expression: "Layer" = 'Material and State' AND "Height" = 1. Click on OK to return to the Feature Class to Feature Class dialog. In Field Map (optional), delete all the fields except Text (Text). Click on OK.


Follow these steps to add the attributes to the Buildings feature class using the **Spatial Join** tool in ArcCatalog.

12. Open **ArcToolbox**, and navigate to **Analysis Tools** | **Overlay**. Double-click on the **Spatial Join** tool, and follow the steps shown in the following screenshot:

Spatial Join
Target Features (1)
)ata_Geoprocess (1)\VeloGIS.gdb\Planimetry\Buildings1 🛗
Join Features (2)
;\Data_Geoprocess (1)\VeloGIS.gdb\DestinationBuilding 🛗
Output Feature Class (3)
)ata_Geoprocess (1)\VeloGIS.gdb\Planimetry\Buildings2
Join Operation (optional)
JOIN_ONE_TO_ONE (4)
✓ Keep All Target Features (optional) (5)
Field Map of Join Features (optional)
CDC (Long) Structure (Text) State (Text) SHAPE_Length (Double) SHAPE_Arca (Double) Text (Text)
Delete
Rename (7)
Merge Rule +
Properties
DestinationDxf
Match Option (optional)
CONTAINS (8)
OK Cancel Environments Show Help >>

-102

- 13. For Target Features, select VeloGIS.gdb\Planimetry\Building1, and click on Add (step 1). For Join Features, select VeloGIS.gdb\DestinationBuilding, and click on Add (step 2). For Output Feature Class, type Building2, and click on Save (step 3). For Join Operation (optional), select JOIN_ONE_TO_ONE (step 4). Check the Keep All Target Features (optional) option (step 5).
- In the Field Map of Join Features (optional) section, erase the SHAPE_Length and SHAPE_Area fields (step 6). Rename the Text (Text) field to DestinationDxf (step 7). For Match Option (optional), select CONTAINS, and click on OK (step 8).
- 15. Again use the **Spatial Join** tool to add two more fields: the **StructureDxf** field from the StructureBuilding standalone feature class and the **StateDxffield** field from the StateBuilding standalone feature class, as shown in the following two screenshots:




16. We have obtained the Building feature class with the field attributes: DestinationDxf, StructureBuilding.dxf, and StateBuilding.dxf. We should populate the Destination fields (the CDC subtype field), Structure (domain field), and State (domain field) with the corresponding fields from the preceding screenshot. Inspect by yourself the codes of the subtype field and the valid values for the domains.

Follow these steps to add subtypes and domain values in the Buildings feature class using the ArcMap context menu.

- 17. Close the ArcCatalog application. Open ArcMap, and add the Building feature class in the Table Of Contents section. Right-click on the Building layer, and select Open Attribute Table. Erase the Join_Count and TARGET_FID fields by right-clicking on the field and selecting Delete Field. Click on the drop-down arrow next to the Table Options button, and select Select by Attributes.
- 18. In the Select by Attributes dialog, for Method, select Create a new Selection. Double-click on DestinationDxf to add the field in the expression section. Click on the IS button, and then click on Get Unique Values to list the unique values for DestinationDxf. Double-click on the NULL value. In the expression section, you should see the following expression: DestinationDxf IS NULL. Click on Verify to check the expression. Click on Apply, and don't close the dialog.
- 19. Right-click on the Destination (CDC) name field, and select Field Calculator. In the warning message, check Don't warn me again, and select Yes. In the Field Calculator dialog, check if you see the CDC= expression above the expression section. In the expression section, type 0; this corresponds to the Unknown subtype. Click on OK.
- 20. Return to the Select by Attributes dialog. In the expression section, build the following expression: DestinationDxf = 'dwelling '. Click on Apply, and don't close the dialog. Repeat step 18, and type 1; this corresponds to the Dwelling subtype. Click on OK.
- 21. Repeat the steps for all values from the **DestinationDxf** field to populate all rows of the **Destination** column.
- 22. Right-click on the **Structure** field, and select **Field Calculator**. In the expression section, add the **StructureDxf** field. Click on **OK**. Right-click on the **State of Building** field, and select **Field Calculator**. In the expression section, add the **StateDxf** field. Click on **OK**.
- 23. For both fields, select the **<Null>** values, and with **Field Calculator**, add the "Unk" values that correspond to the Unknown value domain.
- 24. Erase all the three source dxf fields because they contain redundant information now.



25. In the **Catalog** window, erase all redundant feature classes, such as Buildings1/2/3 and Destination/ Structure/StateBuilding, as shown in the following screenshot:



26. Add features and attributes to the Parcels, SideWalk, and Streets feature classes from the corresponding .dxf files.

You can find the <code>VeloGIS</code> file geodatabase and the expressions files (steps 10 and 11) in \dots \Data\Geoprocessing\MySpatialJoinResults.

How it works...

At step 2, we defined the coordinate reference system for every .dxf dataset. ArcCatalog has created a projection file (prj) for every CAD feature dataset. Before importing a CAD file into the VeloGIS.gdb geodatabase, it is necessary to examine carefully the table of the CAD annotation, polygon, or polyline feature class. It's important to identify the relevant attributes for our feature class before loading the features and attributes in our geodatabase.

There's more...

Open **Windows Explorer**, and notice the size of our VeloGIS.gdb file geodatabase—it's around 1.5 MB. In ArcCatalog, right-click on VeloGIS.gdb, and navigate to the **Administration** | **Compact Database** option. Read carefully what the compact process means. Return to Windows Explorer, and notice the size of our VeloGIS.gdb—it's around 500 KB.

See also

If you want to see all your attribute values for the Building layer as complex labels in Data View, please refer to Chapter 6, Building Better Maps

Using spatial adjustment

Spatial adjustment allows you to spatially adjust the location of a dataset based on a reference dataset through the following processes: transformation, rubbersheet, and edge snap. In general, these processes are used to improve the planimetric accuracy of features from a feature class. In this recipe, we will learn how to adjust a feature class using an affine transformation. The concepts and recommendations from the *Georeferencing raster data* recipe of *Chapter 3, Working with CRS*, are still valid.

Getting ready

In the previous recipe, we added data from the .dxf source datasets to the VeloGIS geodatabase as feature classes. The vectors that came from the RoadCenterLine. dxf dataset have a local cartesian coordinate system. We will consider that the derivate CenterLines feature class has the source coordinate system.

All other dxf datasets are in the right coordinate system, that is, Pulkovo 1942 Adj 58 Stereo 70 (EPSG:3844). We will consider that the derivate Streets and Parcels feature classes have the destination or target coordinate system.

The displacement links are connecting the source location to the destination location. The affine transformation needs at least three links in order to perform the transformation. We will create those links manually using a control point file named ControlPoints.txt. This text file contains a list of five destination coordinates (X, Y).

How to do it...

Follow these steps to perform a spatial adjustment in ArcMap:


 Start ArcCatalog. Go to <drive>:\PacktPublishing\Data\Geoprocessing, and select the DXF folder to see the RoadCenterLine.dxf dataset. Expand the RoadCenterLine CAD feature dataset and preview the features from the CAD Polyline feature class. Right-click on the feature dataset, and navigate to Properties | General. The coordinate system is not specified. Click on the Coordinates tab to see CAD Dataset Extends. The coordinate values are very small, and this indicates that vectors were created using an ungeoreferenced scanned map as background source.

-106

- 2. Go to ..Geoprocessing \ VeloGIS.gdb\Planimetry. Right-click on the CenterLines feature class, and navigate to Load | Load Data. Set the following parameters from the panels:
 - Set the Input data parameter as ... \Geoprocessing \DXF\ RoadCenterLine.dxf:Polyline
 - Check I do not want to load all features into a subtype
 - Target Field (destination) and Matching Source Field (source):

```
Type [short int] = <None>
Name [string] = <None>
```

- Check Load all of the source data
- 3. Click on **Finish** to load the features. Preview the Buildings1 feature class in ArcCatalog to check if the polygon streets were loaded.
- 4. Preview the CenterLines feature class in ArcCatalog to check whether the polyline streets were loaded.
- Close ArcCatalog. Open ArcMap, and add the Streets, Parcels, and CenterLines feature classes. In the Table Of Contents section, right-click on the CenterLines layer, and select Zoom To Layer. Inspect the data.
- 6. Let's add the **Spatial Adjustment** toolbar by navigating to **Customize** | **Toolbars**. On the **Editor** toolbar, navigate to **Editor** | **Start Editing**.
- We will declare the layer we want to adjust from the Spatial Adjustment toolbar. Navigate to Spatial Adjustment | Set Adjust Data. Click on the All features in these layers option, and check only CenterLines. Click on OK.
- 8. We will choose the adjustment method by navigating to **Spatial Adjustment** | **Adjustment Methods** | **Transformation-Affine**.
- 9. On the Editor toolbar, go to Editor | Snapping | Snapping Toolbar and check only End Snapping.
- 10. Open View Link Table from the Spatial Adjustment toolbar. The table is empty. You will add the control points from a text file. Navigate to Spatial Adjustment | Links | Open Control Points File. Select the Control Points.txt file from <drive>:\ PacktPublishing\Data\Geoprocessing. Click on Open.



11. There are five *destination points*, as shown in the following screenshot:

- 12. Let's add the source points. Right-click on the first point from the **Control Points** window, and select **Add Link**. Click on the first point (**P1**) from the ArcMap display area to connect the link with the source point. Use the *F*5 key from time to time to refresh the view and see the links.
- 13. Repeat step 10 for all points. Close the **Control Points** window, and open **View Link Table** from the **Spatial Adjustment** toolbar, as shown the following screenshot:

ID	X Source	Y Source	X Destination	Y Destination	Residual Error	Delete Link
6	6.223200	130.595400	589868.719000	327472.699000	0.000361	
7	87.850200	129.879700	589950.346000	327471.984000	0.000285	Close
В	122.623300	43.787900	589985.119000	327385.892000	0.000162	
9	24.457700	2.303800	589886.953000	327344.408000	0.000105	
10	-8.999600	60.412600	589853.496000	327402.517000	0.000300	



- 14. Notice the estimated individual residual error and the RMS error. Save the links to a text file by navigating to **Spatial Adjustment | Links | Save Links File**. Save it in <drive>:\PacktPublishing\ Data\Geoprocessing as AdjustmentLinks.txt. You can see the file using any text editor (for example, WordPad).
- 15. Close **View Link Table**. Go to **Spatial Adjustment**, and select **Adjust**. Your features from the CenterLines layer were transformed to destination coordinate system.
- In the Table Of Contents section, right-click on the Streets layer, and select Zoom To Layer. Inspect the results. Stop the edit session by navigating to Editor | Stop Editing.
- 17. Save your map document to <drive>:\PacktPublishing\ Data\ Geoprocessing as MySpatialAdjustment.mxd.

How it works...

It is a useful practice to apply topological rules before and after the spatial adjustment for all new feature classes derived from the .dxf datasets. Also, don't forget to save the RMS value; it could be mentioned in the history of your dataset (*Lineage* section) from *Metadata*.

There's more...

Using the **Attribute Transfer** tool, we will update the name of the street from the CenterLines and Parcels layers based on the attribute values of the Streets layer. Follow these steps to add attribute values using the **Attribute Transfer** tool from the **Spatial Adjustment** toolbar:

- Open MySpatialAdjustment.mxd with ArcMap. In the Table Of Contents section, we have Streets, Parcels, and CenterLines layers. Let's add the SideWalk features from VeloGIS.gdb\Planimetry.
- 2. Start the edit session by navigating to **Editor** | **Start Editing**. On the **Snapping** toolbar, check only **Edge Snapping**.

Attribute Transfer Mappi	ng	X
Source Layer	(1)	Target Layer
Streets		▼ CenterLines ▼
SHAPE_Length SHAPE_Area		
Matched Fields	<u>A</u> dd	Auto Match (2)
Туре		Туре
Name	III	Name
		F
Transfer <u>G</u> eometry	(3)	<u>R</u> emove
		OK Cancel

3. On the **Spatial Adjustment** toolbar, navigate to **Spatial Adjustment | Attribute Transfer Mapping**, and go through all the steps shown the following screenshot:

- 4. Uncheck the Transfer Geometry option (step 3), and click on OK.
- 5. Open attribute tables for the Streets and CenterLines layers, as shown in the following screenshot:

<u>File Edit View B</u> ookmarks	Insert Selection Geoprocessing Customize Windows Help
: 🗅 👩 🖬 🖨 i % 🗿 🛍 🗙 i	🔊 🗠 🗄 🗸 1:600 🔹 😴 📰 🗊 🗊 🗊 💭 📴
	- 🕅 + · · · 🐂 🚯 🥖 📲 🗄 Editor + ⊨ · ト _ル ∠ 📲 🚳 🖓 🖓 🔅 🖄 📾 📾 📾 🖓 🐼 🕬 🕬 🚥
	Spatial Adjustment • 💺 📌 🌮 🚫 🖽 🖂 🐙 🧮 🚰 💂 Snapping • 🔿 🖽 🗖 д
	* × Aurel Vlaicu Streets: Edge
8: 📮 🗇 📮 🗄	Drobeta
🖃 😅 Layers	
CenterLines	CenterLines: Edge
all other values>	(a) Decia
Туре	
Avenue	Aure/ Vlaicu
- Others	
Street	
— Unknown	
SideWalk	Table - CenterLines
	[] - 뭡 - 唱 🚱 🗵 💩 🗙
Streets Streets	Streets × CenterLines
Type	OBJECTI SHAPE* Type Name SHAPE L OBJECTID* SHAPE* Type Name S
Avenue	OBJECTI SHAPE Type Name ShAPE_L ODJECTID Shape Type Name S
Others	2 Polygon Street Aurel Viaicu 159.1 ≡ 2 Polytine <null> <null></null></null>
Street	3 Polygon Avenue Dacia 274 3 Polyline <null> <null></null></null>
Unknown	4 Polygon Street Drobeta 177.C < III
□ Parcels	
	II I I I I I I I I I I I I I I I I I I
	Streets CenterLines
	589899.582 327402.57 Meters

- 6. Select the Attribute Transfer tool from the Spatial Adjustment toolbar.
- Click on the edge of the street in the Streets layer (step 1). Click on the feature in the CenterLines layer (step 2). Your features will be flashed, and the Type and Name columns of the CenterLines layer will be updated.
- 8. Repeat step 7 for every feature from the CenterLines layer. Save the edit by navigating to **Editor** | **Save Edits**. To update the **StreetName** field for the Parcels layer, please repeat steps 3 to 7.



In the **Attribute Transfer Mapping** window, we should select the Streets layer as source and the Parcels layer as target. To add the source (**Name**) and target (**StreetName**) fields in the **Matched Fields** section, use the **Add** button

9. Save and stop the edit session; save your map document.

You can find the results of this section at ...\Data\Geoprocessing\ MySpatialAdjustmentResults.

Using common tools

There are three main classes of geoprocessing tools:


- Data extraction (for example, clip and select)
- Overlay (for example, intersect and spatial join)
- Proximity (for example, buffer and point distance)

With geoprocessing tools, we can perform geoprocessing operations. The geoprocessing operations are used to obtain new feature classes or nonspatial tables for a specific analysis.



Getting ready

In this exercise, we will perform an analysis to identify the possible consequences of creating a cycling infrastructure on Dacia Avenue, taking into account the existing road network, as shown in the following image:



Both sides of the street contain the following elements:

- ► One 2-meter-wide footway for pedestrians' movements
- ▶ Two 3.2-meter-wide lanes for moving and stationary vehicles
- One 2-meter median used to separate the roadway from the cycling infrastructure
- One 1.7 meter cycle lane

Suppose that we add two 1.7-meter-wide cycle lanes to the existing road network. We should answer the following questions:

- What is the total area of the expropriated parcels?
- How many buildings should be demolished?


We will continue to use the feature classes from the previous recipe Using spatial adjustment.



How to do it...

Follow these steps to analyze your data using different geoprocessing operations:

 Start ArcMap. Open the existing map document MySpatialAnalysis. mxd from <drive>:\PacktPublishing\Data\ Geoprocessing\ MySpatialAdjustmentResults. At the end of this exercise, we will obtain the following results:



2. In the Table Of Contents section, right-click on the CenterLines layer, and navigate to Properties | Definition Query | Query Builder. Build the following expression: Name = 'Dacia', and click on OK. Now, you see only the Dacia Avenue feature.



3. Open **Catalog** and **ArcToolbox**. In **ArcToolbox**, expand **Analysis Tools**. Go to the **Proximity** toolset, and double-click on the **Buffer** tool to open the dialog, as shown in the following screenshot:

N Buffer	
Input Features	
CenterLines 🗾 🖻	
Output Feature Class	
ySpatialAnalysis\VeloGIS.gdb\Planimetry\Buffer12.1	
Distance [value or field] Linear unit	
12.1 Meters -	
○ Field	=
▼	
Side Type (optional)	
End Type (optional) FLAT	
Dissolve Type (optional)	
LIST 👻	_
Dissolve Field(s) (optional)	
OBJECTID	
Type	
SHAPE Length	
<	
OK Cancel Environments Show Help >>	
	_

4. For Input Features, select CenterLines. For Output Feature Class, go to VeloGIS. gdb\Planimetry, and type Buffer12. For Distance, type 12.1, and set the unit as Meters. The 12.1 meters represent half the width of the street profile. For Side Type, select FULL. For End Type, select FLAT. For Dissolve Type, select LIST. In Dissolve Field(s), check the Name field and click on OK. Add the Buffer12 feature class in the Table Of Contents section.

-114-

		1.0		
Input Features				^
			- 🖻	
Features	Ranks		+	
Buffer 12			×	
Parcels				
Output Feature Cla	ass			
nalysis\VeloGIS.g	db\Planimetry	/Expropriated	Parcels 🔁	
JoinAttributes (opt	ional)			
ALL			•	
XY Tolerance (option	onal)	Meters		
Output Type (optic	(leng	Meters	•]	
INPUT	a naty		•	Ŧ
•	111		•	
OK Cano	el Envi	onments	Show Help >>	

5. Let's extract the parcels that should be expropriated from the Parcels feature class:

6. In ArcToolbox, go to the Analysis Tools | Proximity toolset, and double-click on the Intersect tool. As Input Features, select the Buffer12 and Parcels layers. For Output Feature Class, go to VeloGIS.gdb\Planimetry, and type ExpropriatedParcels. Click on Save. For Join Attributes (optional), select ALL. For Output Type, select INPUT. Click on OK. ExpropriatedParcels is added to the Table Of Contents section. Right-click on ExpropriatedParcels, and select Open Attribute Table. Right-click on the SHAPE_Area field, and select Statistics. Inspect the statistics.

Next, you will check if there are buildings that should be demolished.

7. From the Selection menu, choose Selection By Location. For the Selection method, choose Select features from. As Target layer(s), check Buildings. As Source layer, choose Buffer12. For Spatial selection method for target layer feature(s), choose Intersect the source layer feature. Check Apply a search distance and type 0.5 with the unit as Meters. Click on OK.



- 8. Save the selected buildings in a new feature class by right-clicking on the Buildings layer and selecting Data Export Data. For Export, choose Selected features. For Output feature class, go to VeloGIS.gdb\Planimetry, and type DemolishedBuildings. Click on OK and YES to add the exported data as a layer in your map.
- 9. Save the map document as MySpatialAnalysis.mxd to ...\Data\ Geoprocessing\MySpatialAdjustmentResults.

You can find the results of this section at ... \Data\Geoprocessing\ MySpatialAnalysisResults.

How it works...


Because we decided to analyze only Dacia Avenue, at step 2, we used the **Definition Query** option to display only the Dacia features from the CenterLines layer. The **Buffer** tool will create polygon zones just around the drawn features. By choosing **LIST** for **Dissolve Type**, and the **Name** field for **Dissolve Field(s)**, we will tell the **Buffer** tool to create a single polygon zone around all features named Dacia. In this way, we worked with the minimum necessary data.

At step 6, we chose the **Intersect** (**Overlay**) tool instead of the **Clip** (**Data extraction**) tool because we want the output feature class to inherit the attributes of both the input feature classes. If we explore the attribute table of ExpropriatedParcels, we will notice some difference in StreetName of the Parcels layer and Name of the buffer (Dacia). In this way, we can make the following identifications:

- ▶ The errors in attribute values for the Parcels feature class
- The parcels that belong to the neighboring streets and that will be affected by the new cycling infrastructure

Creating models

According to the online ESRI GIS Dictionary, a **model** is an abstraction of reality used to represent objects, processes, and events. In ArcGIS, a geoprocessing model is created with the **Model Builder** built-in application, as shown in the following screenshot:





A model contains a process or more connected processes that are automatically executed when the model is run. A process consists of three elements: an input dataset (blue element), a tool (orange element), and an output dataset (green element). A geoprocessing model helps us to use various analysis operations and to create new data in a continuous workflow. In this way, the geoprocessing workflow can be reused and shared with other users. In ModelBuilder, you can use three basic types of elements:

- Variables (for example, input or derived data, buffer distance value, and SQL expression)
- Tools (for example, system tools such as buffer and intersect)
- Connectors (for example, data connector)

Another important aspect of a model is **Environment settings**. **Environment settings** refers to additional parameters, such as output geodatabase for the results, output coordinate system, or if the field domain descriptions should be transferred to the derived data. **Environment settings** has a hierarchical approach and affects the result of the workflow.



For more details about **Environment settings**, please refer the online *ArcGIS Help (10.2)* by navigating to **Desktop** | **Geoprocessing** | **Environment settings**.

Getting ready


In this exercise, we will build a model that will repeat the analysis steps from the previous recipe *Using common tools*.

Feature classes	Tools (ArcToolbox)
CenterLines	Buffer (Distance = 12.1 as model parameter)
(Model parameter)	Select("Name" = 'Dacia')
	Intersect
Parcels	Summary Statistics (SUM for SHAPE_Area)
(Model parameter)	
	Select Layer By Location
Buildings	Feature Class to Feature
(Model parameter)	

We will use the following feature classes and tools in the BikeLane model:



The following workflow model provides an overall view of the VeloGIS project:



The preceding diagram shows five geoprocessing tasks:

- Create a buffer of 12.1 meters around the Dacia Avenue center line. The output is intermediate data because it is used as an input for the intersect process (the **Intersect** tool).
- Intersect the buffer with the Parcels layer to obtain the parcels that should be expropriated. The ExpropriatedParcels output is considered as an intermediate result because it is used as an input for the statistic process (the Summary Statistics tool).
- Create a file geodatabase table that contains the total area of parcels. The Sum_ Area Expropiated output table is the final data.
- Select the buildings that intersect with the 12.1-meter buffer. The output is an intermediate result, and it is used as an input for the process of creating features (the Feature class to Feature tool).
- Create a new feature class based on the selected buildings that should be demolished. The DemolishedBuildings output is the final data.

How to do it...

Follow these steps to build and use a simple model in the ModelBuilder environment:

- Start ArcMap. Open the existing map document MyModel.mxd from <drive>:\ PacktPublishing\Data\Geoprocessing\MyModel.Our map contains the same layers from the previous recipe. Open Catalog and ArcToolbox.
- 2. In **Catalog**, set the default geodatabase to VeloGIS.gdb. Right-click on the geodatabase, and choose **Make Default Geodatabase**.

-118

- 3. Let's create the model. Right-click on VeloGIS.gdb, and navigate to New | Toolbox. Right-click on the new Toolbox, and navigate to New | Model.
- 4. From the **Model** menu, navigate to **Model** | **Properties** | **General**. For **Name** and **Label**, type BikeLane. For **Description**, type the project description from the *Getting* ready section.
- 5. Check the **Store relative path names** box. Click on **Apply**. Select the **Environments** tab, and expand **Workspace**. Check **Current Workspace**, and select **Values** to confirm that VeloGIS.gdb is your current workspace. Click on **OK**, **Apply**, and again on **OK** to return to the blank BikeLane model.
- 6. From the **Model** menu, navigate to **Model** | **Diagram Properties** | **Symbology**. Select **Style 2**, and click on **OK**.
- Let's add some processes to the BikeLane model. Please follow the workflow diagram from the Getting ready section. Navigate to ArcToolbox | Analysis Tools | Proximity, select and drag-and-drop the Buffer tool to the BikeLane model window.

The white model elements are in the first state, that is, *they are not ready to run*. This is because it is missing the input. You will add the input, as shown in the following steps.

- 8. From the Insert menu, select Add Data or Tool. From <drive>:\ PacktPublishing\Data\Geoprocessing\MyModel\ VeloGIS.gdb\ Planimetry, select the CenterLine feature class. Click on Add.
- The CenterLine feature class will become the input element for the Buffer tool. To add a connection, select the Connect tool from the Standard toolbar. First click on CenterLine, and then click on the Buffer tool and choose Input Features.
- 10. With the **Select** tool (black arrow), double-click on the **Buffer** tool, and set the following parameters:
 - Input Feature: For this, the CenterLines feature class is already mentioned
 - Output Feature Class: For this, the default path is already mentioned; type the name of the new feature class—BufferCenterLine
 - Distance: This should be 12.1 with the unit as Meters
 - Set the last parameters from steps 3 and 4 of the Using common tools recipe; click on **OK**

Now, your colored model elements are in the second state, that is, *they are ready to run*. You will continue to add tools, as shown in the following steps.

11. Navigate to ArcToolbox | Analysis Tools | Extract, and select and drag-and-drop the Select tool to the BikeLane model window.



- 12. The BufferCenterLine output will become the input element for the Select Data tool. To add a connection, select the **Connect** tool, click on BufferCenterLine, click on the Select Data tool, and choose Input Data Element. All our model elements are colored. With the Select tool (black arrow), double-click on the Select tool. Set the following parameters:
 - Input Feature: This already has the BufferCenterLine layer
 - Output Feature Class: For this, the default path is already mentioned; type only the name of the feature dataset and new feature class: Planimetry\ BufferBikeLane
 - **Expression (optional):** For this, type "Name" = 'Dacia'; click on **OK**.
- 13. Navigate to ArcToolbox | Analysis Tools | Overlay, and select and drag-and-drop the Intersect tool to the BikeLane model window.
- 14. The BufferBikeLane output will become the input element for the Intersect tool. To add a connection, select the Connect tool, click on BufferBikeLane, click on the Intersect tool, and choose Input Features. You will add a second input layer. From the Insert menu, select Add Data or Tool, and select the Parcels feature class. Click on Add to close and return to the BikeLane model window. Connect Parcels to the Intersect tool, and choose Input Features.
- 15. With the **Select** tool (black arrow), double-click on the **Intersect** tool. For **Output Feature Class**, the default path is already mentioned; type only the name of the feature dataset and new feature class: Planimetry\ExpropriatedParcels. Leave the other parameters unchanged, and click on **OK**.
- 16. Click on the **Auto Layout** and **Full Extent** buttons to rearrange the elements and better see the whole ready-to-run model. Navigate to **Model | Save** to save the changes.
- 17. Navigate to ArcToolbox | Analysis Tools | Statistics, and select and drag-anddrop the Summary Statistics tool to the BikeLane model window. Connect ExpropriatedParcels to the Summary Statistics tool, and choose Input Table. The model elements remain white, that is, they are not ready to run. Double-click on the tool. For Output Table, type SUM_Area_Expropriated at the VeloGIS.gdb level. For Statistics Field(s), select SHAPE_Area. For Statistic Type, choose SUM. Click on OK.
- 18. To validate the model, select the **Validate Entire Model** tool. To run the model, navigate to **Model** | **Run Entire Model**. Click on **Close** after the process is completed.

Now, your colored model has a drop shadow behind the tools and derived data elements. The model is in the third state, that is, *it has already been run*.



- 19. Close the model. In the **Catalog** window, check if the new feature classes were created.
- 20. We can use our **BikeLane** tool by right-clicking on it and selecting **Open**. Into the **BikeLane** dialog window, we can control only the **Environments** option and the **OK** button. We could also see the project description if we click on **Show Help**. If we click on **OK**, we can again run our tool, and our results will be in superscript in the geodatabase. Click on **OK** and on **Close**.
- 21. You can find the intermediated model at ... \Data\Geoprocessing\ MyIntermediatedModel.
- 22. As we could notice, there is some inconvenience when we use the **BikeLane** tool; we don't have control over the parameters of BikeLane, and the feature classes were not added in the **Table Of Contents** section.

Let's declare the model parameters for BikeLane in order to have more control over the **BikeLane** tool results.

- 23. In Catalog, right-click on the BikeLane tool, and select Edit. Right-click on the CenterLines input, and select Model Parameter. Our blue input will have a letter P. Right-click on the Buffer tool, and navigate to Make Variable | From Parameter | Distance [value or field]. Click on Auto Layout to see all elements. To declare this value variable as a model parameter, right-click on the Distance [value of field] input value, and select Model Parameter. Right-click on the Parcels input, and select Model Parameter.
- 24. As a final improvement, we will specify the layers to be added in the **Table Of Contents** section. Right-click on the BufferBikeLake derived data, and select **Add To Display**. Repeat this step for the ExpropriatedParcels and SUM_Area_ Expropriated derived data.

121—

- 눡 BikeLane ÷ Parcels CenterLines WyModel\VeloGIS.gdb\Planimetry\CenterLines e* No description available ◯Distance [value or field]◯ Linear unit ! Document your 12.1 Meters • model Field + Parcels r i MyModel\VeloGIS.gdb\Planimetry\Parcels 111 OK Cancel Environments... << Hide Help Tool Help
- 25. Save and close the model. In **Catalog**, double-click on the **BikeLane** tool. We should see the following screenshot:

- 26. You can use feature classes with different names and change the buffer distance. Close the tool window.
- 27. Try to complete the model with more processes using the following three segments:
 - The workflow diagram from the Getting ready section
 - Steps 7 to 8 from the Using common tools recipe
 - The final model from the MyModelResults folder

-122

How it works...

From the beginning, we set one of the most important parameters: Workspace. We defined the current workspace at the application-level environment (for all tools). The BikeLane model will inherit this environment setting parameter, and all intermediate and final data results will be stored by default in VeloGIS.gdb. If you want to check and modify the current and scratch workspace at the application level, please navigate to **Geoprocessing** | **Environments** | **Workspace**.

At step 5, we used relative paths for our model. If we change the folder where we keep the VeloGIS.gdb geodatabase, the model will still run properly.

At step 17, we mentioned that the SUM_Area_Expropriated table will be saved at the geodatabase level. A nonspatial table cannot be created in a feature dataset. Please recall from *Chapter 1*, *Designing Geodatabase*, that a feature dataset is a collection of feature classes that have the same coordinate system. A nonspatial table does not have a spatial component.

If we try to run the **BikeLane** tool from ...\Data\Geoprocessing\MyModelResults\ VeloGIS.gdb, using the ArcCatalog application, an error will occur: **ERROR 000732 Buildings: Dataset Buildings does not exist or is not supported**. This is because we have used the **Select Layer By Location** tool to select the buildings from the Buildings layer in ArcMap. This tool selects the feature from a layer (input data). A layer is specific to an ArcMap environment. In conclusion, our final model will run only in ArcMap. Open MyModelResults. mxd, and use the **Catalog** window to run the **BikeLane** tool.

See also

 If you want to change the symbols for your layers in ArcMap, please refer to Chapter 5, Working with Symbology

5 Working with Symbology

In this chapter, we will cover the following topics:

- Managing styles
- Modifying symbols
- Creating custom symbology
- Using proportional symbology
- Using the symbol levels
- Using representation

Introduction

An important aspect of map design is data **symbology**. For a final cartographic product, cartographers must classify, generalize, and symbolize different spatial data. A map reader should be able to recognize the symbols used by cartographers, and analyze and understand the reality represented in the final map.


Symbols can vary in graphic characteristics in order to express differences, hierarchy, and importance of the represented features from a qualitative or quantitative point of view. Choosing the right size, color, shape, or position (center or offset) for a symbol is crucial for the final message of the map.

In this chapter, you will learn how to create and store a set of customized symbols, and draw rules in your maps using **Style Manager** and **Representations**. You will also apply the proportional symbology according to quantitative values of the attribute value.

Working with Symbology

Managing styles

A style is a collection of symbols, colors, and map elements (such as legend, scale, north arrow, border, and reference system) used to create a map. A style set organizes symbols and map elements in a predefined structure. You can use the system styles or personal styles that contain certain elements for specific types of maps. In a system style, the gray folder icons indicate that the style set is read-only. In a new style set, the white folder icons indicate that they are empty, and the yellow folder icons indicate that they are populated with customized elements, as shown in the following screenshot:



A style set is actually a single file with a .style extension that can be read in ArcMap. The style file can be accessed with Windows Explorer and saved as a backup or sent to other users by e-mail. A personal style is not dependent on the ArcMap document (*.mxd) in which it was created and can be used by different map documents.

The system style files are installed at: <ArcGIS HOME>\Desktop10.2\Styles.

The default personal style is saved at (Windows operating system): <install_drive>:\ Users\<username>\AppData\Roaming\ ESRI\Desktop10.2\ArcMap.



Getting ready

You can work with a style in ArcMap using the **Style Manager** dialog box. The **Style Manager** dialog box lets you create and organize styles and their contents. You can create, cut, copy, paste, rename, and modify the style contents in personal styles. You can also copy symbols, colors, or other map elements from system styles (read-only) and paste to your personal styles, where you can modify them. Before you modify default ArcGIS symbols or create new symbol libraries, you should create a new style set in which to keep all of your changes. In the next step, you will create a new style set for the purpose of applying standard symbols for a topographic map at scale 1:5,000.

How to do it...

Follow these steps to create a new style set using the Style Manager dialog box:

- 1. Start ArcMap, and open a new blank map document.
- 2. Navigate to **Customize menu** | **Style Manager**. The **Style Manager** dialog box shows two style sets. The first one is a default personal style and the second one, named ESRI.style, is a default system style.

Style Manager		Style References	23
Perference Systems Ma Maplex Labels Shadows Area Patches Lin Labels Labels Representation Markers Ref North Arrows Scale Scale Bars Color Ramps Color Ramps Color Borders Bar Colors Vectorization Settings Fill Symbols Fill Maplex Labels Representation Markers	ference Systems applex Labels adows ea Patches bels presentation Markers rith Arrows ale Bars gend Items ale Bars gend Items ale Texts lor Ramps rders ckgrounds lors ctorization Settings Symbols re Symbols arker Symbols spresentation Rules	Image: Constraint of the second se	

3. Navigate to Styles | Create New Style, as shown in the following screenshot:


4. In the **Save As** dialog box, navigate to <drive>:\PacktPublishing\Data, type TOP05k, and click on **Save**. Click on **OK**. The structure of TOP05k.style is empty.



Working with Symbology

Now, copy a linear symbol from ESRI.style and paste it into your TOPO5k.style, where you can rename and modify the symbol:

- 1. In the **Style Manager** dialog box on the left-hand side, navigate to **ESRI.style | Line symbols**. In **Style Manager**, right-click on the symbol named River, Navigable and select **Copy**.
- In Style Manager on the left-hand side, navigate to TOP05k.style | Line symbols. In Style Manager on the right-hand side, in the empty space, right-click and select Paste. You should see something similar to the following screenshot:



-128

- 3. The symbol was saved in your personal style set. Notice that the white symbol folder icon became yellow. This indicates that the folder is populated with customized elements.
- 4. Close the **Style Manager** dialog box. The TOPO5k.style folder you created is saved even if your map document is not. Close ArcMap.

How it works...

The **Style References** dialog box lists all the system style files and the default personal style. The checked styles will be referenced into your map document. Referencing one or more styles means that its contents will be displayed in the **Symbol Selector** window. The **Style Manager** dialog box lets you see the styles you created before. You can add more styles to **Style Manager** by navigating to **Styles** | **Add Style to List**, and if you don't want to see one of them anymore, uncheck it in **Style References**. The unchecked style files are still in **Style References** and in your directory too. To erase them from your directory, you should use Windows Explorer or ArcCatalog applications.



In ArcCatalog, navigate to **Customize** | ArcCatalog Options. Select the **File Types** tab. Define the .style type by selecting **New Type**. Fill the **File extension** and **Description of type** sections. In ArcCatalog navigate to **View** | **Refresh**. With those settings, ArcCatalog will be able to see the style files.

There's more...

You can change the list of styles displayed in the **Style References** dialog box by changing the style path setting with the **ArcMap Advanced Settings Utility** parameter located at <ArcGIS HOME>\Desktop10.2\Utilities\AdvancedArcMapSettings.exe.

Working with Symbology -

Double-click AdvancedArcMapSettings.exe to open ArcMap Advanced Settings Utility and select the System Paths tab. In the All users section, go to Styles path. You can change the location of .style files by navigating to <drive>:\PacktPublishing\Data, as shown in the following screenshot:

- 1	Linear Referencing	TOC / Data	Print / Expo
a Frame	Miscellaneous	Editor	Advanced Editin
C:\Program	m Files (x86)\ArcGIS\Deskto	p10.2\MapTemplates\	
C:\Program	m Files (x86)\ArcGIS\Deskto	p10.2\Locators	
C:\Users\c	dana\AppData\Loca/\Temp		
	S ADMIN privil	s ADMIN privileges to update) E:\PacktPublishing\Data C:\Program Files (x86)\ArcGIS\Deskto	s ADMIN privileges to update) E:\PacktPublishing\Data C:\Program Files (x86)\ArcGIS\Desktop10.2\MapTemplates\ C:\Program Files (x86)\ArcGIS\Desktop10.2\Locators

If ArcMap is open, you must close the session and restart the application for your changes to take effect.

When you restart ArcMap, the **Style References** dialog box will show all your style files created in the previous steps. You can also **Reset all values to default** in **ArcMap Advanced Settings Utility**.

See also

► For information about modifying and creating new symbols, please refer to the upcoming *Modifying symbols* and *Creating custom symbology* recipes

Modifying symbols

The geographic features are graphically represented by symbols. Symbols have characteristics that can be varied in order to emphasize the differences, hierarchy, or importance of the features on a map.

The graphic characteristics or visual variables are referring to symbol size, color value (gray tone), hue (color), texture (pattern), orientation, and shape. These variables are applied individually or in combination to point, line, and area symbols depending on the type of data to be represented on a map.


For qualitative data, you can vary the following symbol characteristics: hue (color), texture, orientation, and shape.

For quantitative data, you can vary the following two symbol characteristics: size and color value (gray tone).

Getting ready

In the next step, we will apply standard topographic symbols for a topographic map at scale 1:5,000.

Symbolize point and line features and try by yourself to symbolize polygon features. Firstly, symbolize one point feature class named Elevation and one polyline feature class named WatercourseL, as shown in the following screenshot:



Secondly, add again WatercourseL in your map document, and symbolize it based on the field named HIC, which defines the hydrologic category.



How to do it...

Follow these steps to symbolize the Elevation and TriangulationPoint feature classes:

- Start ArcMap and open a new map document. Click on Add Data button. Load the Elevation feature class from <drive>:\PacktPublishing\Data\TOPO5000. gdb\Relief.
- In the Table Of Contents section, right-click on the Elevation layer and navigate to Properties | Symbology | Features | Single symbol. In the Symbol section, click on the symbol to open the Symbol Selector dialog box, as shown in the following screenshot:

Symbol Selector		1	- 1	-	×
Point feature		- @) 🔊 🗄 🗸	Current Symb	loo
Search: 🔘 Al	l Styles	Referenced	Styles		
Ordnance Surv	vey		^		0
0	o	Δ			
Boundary post f	Boundary half nereing symbol	Triangulation point		<u>C</u> olor:	-
←	+			<u>S</u> ize:	10
Bench mark	Spot height	Pylon		<u>A</u> ngle:	0.00
				Edit	Symbol
0	← *	x		Save As	<u>R</u> eset
Point feature	Flow arrow	Roofed building indicator			
	冬	Â			
Glasshouse	Positioned	Positioned	=		
indicator c	coniferous tree	non-coniter		Style Re	e <u>f</u> erences
	04	令	-	ОК	Cancel

- 3. In the **Symbol Selector** dialog, navigate to **Style References** | **Ordnance Survey**. Click on **OK** in **Style References** to return to the **Symbol Selector** dialog. In the **Symbol Selector** dialog, check **Referenced Styles**, type point feature and click on the **Search** button on the right. This will find the symbol Point feature from Ordnance Survey.style.
- 4. Select the Point feature symbol. Let's change the Point feature symbol.



5. To change color, navigate to **Color** | **More Colors**. In the **Color Selector** dialog, select the **Color** tab and choose the **RGB (Red Green Blue)** color model. To set the color to sepia, type the values 112, 66, and 20 as shown in the following screenshot:

Co	lor Se	elector			
С	olor	Properties		RGB 🔻	
R		Û		112	
G		0		66	
в	-0-			20	
H			ОК		
			UK	<u>C</u> and	ser j

- 6. Click on **OK**. For **Size**, type 10 points. Select the **Edit Symbol** button to notice that your symbol is a **Character Marker Symbol** that has a single layer. Click on **OK** three times to close all dialog windows.
- 7. In the Table Of Contents section, right-click on the Elevation layer and select Save As Layer File. Save your layer as Spot Elevation.lyr to <drive>:\PacktPublishing\Data.
- 8. Navigate to File | Save as, and save your map document as ModifySymbol.mxd.

Follow these steps to symbolize the WatercourseL feature class:

- 9. Click on the **Add Data** button, and load the WatercourseL feature class from ...\Data\TOPO5000.gdb\Hidrography.
- 10. In the **Table Of Contents** section, the WatercourseL layer is symbolized based on its subtypes by default (HAT field). Double-click on the WatercourseL layer to open the **Layer Properties** window.
- Uncheck the <All other values> parameter. Double-click on the line symbol of subtype with the value 4 Canalized stream. In the Symbol Selector dialog, select Color: Cretan Blue (10th column, 3rd row). For Width, select 2, and click on OK.
- 12. Symbolize the rest of the subtypes as follows:
 - Greek: Color Cretan Blue, width 1
 - 2 River: color Cretan Blue, width 3
 - □ 1 Stream: Color Cretan Blue, width 1.7
 - 0 Unknown: Color Mars Red, width 0.5
- 13. Select Label: HAT, type Type of water course, and click on OK.



- 14. Save your WatercourseL layer as WatercourseL_HAT.lyr to <drive>:\ PacktPublishing\Data.
- 15. In the Table Of Contents section, uncheck the Watercourse layer.
- 16. To add the WatercourseL feature class, again right-click on the layer and select Copy. Right-click on the name of the current data frame called Layers and select Paste Layer(s). In the Table Of Contents section, click on the name of the layer to rename it as WatercourseL HIC.
- 17. Double-click on the WatercourseL HIC layer to open the Layer Properties window. Change the Value Field parameter to Hydrologic category and click on the Add All Values button. Uncheck the <All other values> button.
- 18. Double-click on the following subtype value: 3 Ephemeral. In the **Symbol Selector** dialog, scroll down and click on the symbol Stream, Intermittent from the **ESRI** default section.
- 19. For **Color**, select Cretan Blue (10th column, 3rd row). For **Width**, select 1, and click on **OK**.
- 20. Symbolize the remaining subtypes as follows:
 - 2 Intermittent: Dashed 6:6, color Cretan Blue, width 1
 - □ 1 Perennial: River, Color Cretan Blue, width 1
 - 0 Unknown: River, Color Mars Red, width 1
- 21. Save the WatercourseL layer as WatercourseL_HIC.lyr to <drive>:\ PacktPublishing\Data.
- 22. Navigate to File | Save as and save your map as MyModifySymbols.mxd at <drive>:\PacktPublishing\Data\MapDocuments.

You can find the results at ... \Data\MapDocuments\Chapter5\ModifySymbol.mxd.

How it works...

Firstly, you have symbolized a one-point feature class named Elevation. The symbols represent qualitative (nominal) data and have the same size with the same hue (color).

Secondly, you symbolized one polyline feature class, WatercourseL based on the field named HAT, which classifies the rank of rivers. The symbols represent quantitative (ordinal) data and have different sizes with the same hue (color). You created a hierarchy by varying the size of symbol. When you use categories to symbolize the data, the **<All other values>** value refers to all other possible field values that are not defined in the list of the unique values (unmatched values).



You unchecked the **<All other values>** value because your layer is symbolized by default based on the subtypes and you assume that your data does not contain errors. You can use the **<All other values>** value if you want to visually validate the attribute values of a subtype or domain field.

You symbolized once again WatercourseL based on the field named HIC, which defined the hydrologic category. The symbols represent qualitative (nominal) data and will have a different shape with the same hue (color). You showed differences by varying the shape of symbols. You have saved symbolized layers in a separate layer file (.lyr). This file saves the path to the physical store of the source data and the way you choose to symbolize the features. Now, try by yourself to symbolize by navigating to the **TOPO5000.gdb** | **LandUse** | **LandUse** polygon feature class base on the field named CAT, which defines land use categories. The symbols will represent qualitative (nominal) data and will have a different texture with the same hue (color). You will show the differences by changing the texture of the symbol.

There's more...

Hue refers to the colors from the visible portion of the electromagnetic spectrum (wavelengths of the electromagnetic radiation from 0.4μ m to 0.7μ m). Hue is defined by mixing the colors Red, Green and Blue (RGB) or by mixing the colors Cyan, Magenta and Yellow (CMY). RGB is the main color system used for televisions and computer screens. CMYK is the main color system used for desktop printing (inkjet or laser) and commercial offset printing. CMYK refers to four basic ink colors: cyan, magenta, yellow and black (the K). HSV is a three-dimensional color space that link hue with value (lightness or darkness) and saturation (colorfulness or purity). When you select color for a printed map, you should use the **Color Calibration Chart** from: arcgis.HOME)

Desktop10.2

plotters<calibrate.mxd.

Creating custom symbology

A symbol is composed of one or more graphic layers. Every symbol layer uses a point, line or area symbol, text, and color to represent a geographic feature. A symbol layer has its own graphic characteristics, such as size, color value, hue, texture, orientation, and shape. Depending on the number, order of drawing, size, form, color, offset, or other graphic characteristics, symbol layers overlap to form a single and distinct symbol.

135

Getting ready

In the next step, you will create standard topographic symbols for a topographic map at the scale 1:5,000. Firstly, you will create a point symbol for the thorny shrub feature, as shown in the following screenshot:

Preview	Pro	operties												
1	Ту	pe: C	harac	ter M	arker	Symb	ol		•]				Units: Points
•••••••••••••••••••••••••••••••••••••••	. 0	Charact	er Ma	rker	Mas	k								
•		<u>F</u> ont:		o B	asken	ville O	ld Fa	ce		•				Size: 14 🗸
☑ ┼		S <u>u</u> bse	et:	Basic	Latin					•				Angle: 5
	-		1		#	<mark>\$</mark>	%	&	1	()	*		<u>C</u> olor:
Layers		+	,	-		/	0	1	2	3	4	5	Ξ	Offset:
v • A •	1	6	7	8	9	:	;	<	=	>	5	@		X: 4.5
✓ · A ✓ . A_		Α	В	С	D	E	F	G	Η	Ι	J	K		Y: 3.5
· · · · · · · · · · · · · · · · · · ·		L	М	Ν	0	Р	Q	R	S	Т	U	v		
		W	х	Y	Ζ	[\]	>	_	1	a	-	
+×↑↓		Unico	de:	33		7								1
🖹 🖹 🖉														

Secondly, you will create a pattern for polygon features from LandUse in accordance with the subtype classification field (CAT).

How to do it...

Follow these steps to create a new point symbol and an area symbol (pattern):

- 1. Start ArcMap and open a new map document.
- 2. Navigate to Customize | Style Manager | Styles | Add Style to List.
- 3. Load the custom style file from <drive>:\PacktPublishing\Data\TOPO5k. style. Click on **OK**.
- 4. In **Style Manager** on the left-hand side, select the TOPO5k.style/ Marker Symbols folder.
- 5. On the right-hand side, in the empty space, right-click and navigate to **New | Marker Symbol** to open the **Symbol Property Editor** dialog box.
- 6. In the Layers section, use the Plus Sign button to add four symbol layers.



- 7. Select the first layer. In the **Properties** section, for **Type**, select **Character Marker Symbol**, and for **Units**, select **Points**.
- 8. In the Character Marker tab, choose Font: ESRI Default Marker, Subset: Basic Latin, Unicode: 40, and Size: 2.83.
- 9. Select symbol layer number two, and set Type: Character Marker Symbol and Units: Points. In the Character Marker tab, choose Font: ESRI Default Marker, Subset: Basic Latin, Unicode: 33, Size: 2.83, OffsetX: -2.55, and OffsetY: -3.40.
- Select symbol layer number three, and set Type: Character Marker Symbol and Units: Points. In the Character Marker tab, choose Font: ESRI Default Marker, Subset: Basic Latin, Unicode: 33, Size: 2.83, OffsetX: -2.55, and OffsetY: 3.11.
- 11. Select layer number four, and set Type: Character Marker Symbol and Units: Points. In the Character Marker tab, choose Font: Baskerville Old Face, Subset: Basic Latin, Unicode: 33, Size: 14, Angle: 5, OffsetX: 4.5, and OffsetY: 3.5.
- 12. Click on **OK**. Rename the symbol MyThornyShrub, and **Category**: LAND USE.

Let's create a pattern for the LandUse polygon features, as shown in the following screenshot:

Symbol Property Editor	and a got and any last	×
Preview	Properties: Type: Marker Fill Symbol Marker Fill Fill Properties	Units: Points 🔹
Layers	Color: Marker Outline © Grid © Random	Marker Fill Fill Properties Offset: X: 17.0000 Y: 17.0000 Separation: X: 34.0000
		Y: 34.0000



The following steps will show you how to create LandUse polygon features:

- 1. In **Style Manager** on the left-hand side, select the TOPO5k.style/Fill Symbols folder.
- In Style Manager on the right-hand side, in the empty space, right-click and navigate to New | Fill Symbol. In the Symbol Property Editor section, go to the Layers section, and use the Plus Sign button to add one more symbol layer.
- 3. For the first symbol layer, set **Type**: Marker Fill Symbol and **Units**: Points. In the **Marker Fill** tab, select the **Marker** button, and choose MyThornyShrub from TOPO5k.style. Click on **OK**. Select the **Grid** check box.
- 4. In the Fill Properties tab, set SeparationX: 34 and SeparationY: 34.
- 5. Select the second layer, and set **Type**: Marker Fill Symbol and **Units**: Points. In the **Marker Fill** tab, select the **Marker** button, and choose MyThornyShrub from TOPO5k.style. Click on **OK**. Select the **Grid** check box.
- 6. In the Fill Properties tab, set OffsetX: 17, OffsetY: 17, SeparationX: 34, and SeparationY: 34.
- 7. Click on **OK**. Rename the symbol as MyThornyShrub, and **Category** as LAND USE. Your fill symbol has been automatically saved into TOPO5k.style.
- 8. Click on Close to close the Style Manager dialog. Close ArcMap without saving.

How it works...

There are 10 types of land use in the feature class LandUse: Arable, Pasture, Meadow, Vineyard, Fruit orchard, Forest, Hydrography, Transportation, Other terrain and Unproductive. In . . . \Data\TOPO5000.style, there are already defined patterns for every type of land use in the **Fill Symbol** section. These patterns have been created based on the point symbols from the **Marker Symbol** section. Notice that the **Name** and **Category** sections are constantly used in the same way for point and fill symbols. This aids in easy identification of all graphic characteristics that describe the same custom symbol (hue, shape, texture).

There's more...

If you want to apply symbols based on a custom style for a subtype, first you have to check whether the **Description** section for the subtype **Code** corresponds exactly to **Name of symbols** from the style file. Follow these steps to apply symbols based on a style:

- Start ArcMap and open a new map document. Click on the Add Data button to load the LandUse feature class from <drive>:\PacktPublishing\Data\TOPO5000. gdb\LandUse.
- 2. In the **Table Of Contents** section, right-click on the LandUse layer, and navigate to **Properties | Symbology | Categories | Match to symbols in a style**.

- 3. Select the style file named TOPO5000.style from <drive>:\PacktPublishing\ Data folder, and press the **Match Symbols** button. Click on **OK**.
- 4. Inspect the results, and save your map document as MyCustomSymbology.mxd to ...\Data\MapDocuments.

Using proportional symbology


Point symbols represent discrete physical features (for example, triangulation points, address locations, fire hydrants, or street signs) or conceptual features (for example, cities by population, population by counties, birth rate, or unemployment rate by country, or disease outbreaks between 1990 and 2014 by region).

ArcMap offers four tools to represent quantitative data:

- Graduated colors: This varies the hue (color) to symbolize the attribute values grouped into a given number of classes.
- Graduated symbols: This varies the size and keeps the hue (color) constant to symbolize the attribute values grouped into a given number of classes.
- Dot density: This keeps the size and hue (color) constant to symbolize the data that is not classified; the number of dots is tied to a certain attribute value.
- Proportional symbols: This keeps the hue (color) and shape constant and varies the size that is tied to the highest and lowest attribute values and a given number of graduated symbols.

Getting ready

In this recipe, you will use point symbols to represent the quantitative attributes of the Counties polygon feature, as shown in the following screenshot:





All the point symbols will have the same color, same shape (circle for instance) and will vary in size to show the exact attribute values.

How to do it...

Follow these steps to visualize quantitative data using the proportional symbols method:

- 1. Start ArcMap and open a new map document. Load the Counties feature class from: <drive>:\PacktPublishing\Data\TOPO5000.gdb\Boundaries.
- 2. In the **Table Of Contents** section, double-click on the Counties layer to open **Symbology** in the **Layer Properties** dialog.
- 3. Navigate to **Quantities** | **Proportional symbols**. This will display the **Layer Properties** dialog, as shown in the following screenshot:

Layer Properties								×
General Source Select	ion Display	Symbology	Fields	Definition Query	Labels	Joins & Relates	Time	HTML Popup
Show: Features	Draw quant	ities usin <u>c</u>	j symbo	l size to show e	xact va	lues.	mport]
Categories	Fields				Data			n II
Quantities Graduated colors	<u>V</u> alue:	Populatio	n	•	0	Exclude	1	
Graduated symbols	<u>N</u> ormalization	none		-	l		J	
Proportional symbols								
Dot density	<u>U</u> nit:	Unknown	n Units	•	ſ	Rotation		
Multiple Attributes	Symbol						~	
	Backgroun		Min Value	e Max 1	Value			
	Appearance	ce Compens	sation (Fla	annery)	<u> </u>			
	Nu <u>m</u> ber of Sym	bols to displ	lay in the	Legend: 5	•			
						OK Ca	ancel	Apply

- 4. In the **Fields** section, for **Value**, select Population.
- 5. In the **Symbol** section, click on the background symbol.
- 6. In the **Symbol Selector** dialog, choose **Fill Color**: Olivine Yellow (6th column, 1st row), and click on **OK** to return to the **Layer Properties** dialog.

140

- Click on the Appearance Compensation (Flannery) check box. This option will slightly increase the size of circular symbols in order to avoid the wrong perception of symbol sizes on your map.
- 8. Navigate to **Min Value** | **Edit Symbol**. In the **Symbol Property Editor** dialog, for **Color**, choose the **Fir Green** option (7th column, 7th row).
- 9. For Size choose 6. Select Edit Symbol and uncheck the Use Outline box. Click on the Mask tab and select Style Halo with Size: 1.
- 10. Click on the **OK** button twice to return to the Layer Properties dialog.
- 11. For Number of Symbols to display in the Legend, select 5.
- 12. Click on the **Exclude** button to open the **Data exclusion Properties** dialog. Select the **Query** tab, and build the following expression: Population = 0.
- Select the Legend tab and the check box Show symbol for excluded data. Navigate to Symbol | Edit Symbol. In the Layers section, use the Plus Sign button to add a new symbol layer.
- 14. Select the new symbol layer. Set Type: Line Fill Symbol and Units: Points. In the Line Fill section, choose Color: Mars Red (2nd column, 3rd row), and Angle: 45.
- 15. Click on **OK** twice to return to the **Data Exclusion Properties** dialog. In the **Data Exclusion Properties** dialog, for **Label**, type No data.
- 16. Click on **OK**. Inspect the results and save your Counties layer as Counties.lyr to <drive>:\PacktPublishing\Data.
- 17. Save your map as MyProportionalSymbology.mxd at ... \Data\MapDocuments.

You can find the results at ... \Data\MapDocuments\Chapter5\ ProportionalSymbology.mxd.

How it works...

You created a correlation between symbol size and ratio data value (quantitative data) by using proportional symbols. After you have gone through steps 7 to 9, you will notice that the **Max Value** symbol has changed proportionally. Since the polygon feature class contains an element with the value 0 for population, you have excluded this data from steps 12 to 16.

141

There's more...

The position of the circles can fall at the edge or outside of the polygon. This is because the circles are positioned at the centroid of their polygons. The centroid of the irregular polygons might lie outside the polygon, as shown in the following screenshot:



If you want to edit one of the circles' position, you should convert them into graphics. Rightclick on the Counties layer, and navigate to **Convert Features to Graphics** | **Only draw the converted graphics**. The **Draw** toolbar offers the tools to edit graphics. To see the polygons from Counties, right-click on the layer and navigate to **Properties** | **Display** | **Feature Exclusion** | **Restore All**. By converting the symbols to graphics, you will remove the link between the symbol and the associated attribute values. This means they will no longer adjust to changes to the attribute values.

Using the symbol levels

As you saw in the *Creating custom symbology* recipe, your symbols have one or many layers. By default, ArcMap controls the drawing order for symbols. The features are drawn based on the order in the **Table Of Contents** section and based on the order from the attribute table of every feature class. The symbol levels allow you to control the order of the feature symbols in **Data View**.

Getting ready

First, you will prepare data for test symbol layers by applying custom symbols to the RoadL feature class subtype. The symbols are already created in TOPO5000.style. When you visualize the data at scale 1:5,000, you will see a lot of graphic errors. To see the errors, use an existing map document named SymbolLevelRoad.mxd from <drive>:\ PacktPublishing\Data. Use the **Default View** and **Advanced View** options to control the drawing order of the symbol layers.

How to do it...

Follow these steps to use layer symbols to correct all graphic errors:

- 1. Start ArcMap and open an existing map document SymbolLevelRoad.mxd from <drive>:\PacktPublishing\Data.
- 2. In the **Table Of Contents** section, right-click on the RoadL layer and navigate to **Properties | Symbology | Categories | Match to symbols in a style**. Click on the **Browse** button to add the ... \Data TOPO5000.style style file. To match the existing symbols with the values of the CND subtype field, press the **Match Symbols** button. Click on **Apply** and on **OK**.
- 3. Go to the **Bookmarks** menu and explore the spatial bookmarks that show you all the graphic errors of the linear symbols.
- 4. To resolve the drawing errors shown by the Forest and Forest 2 bookmarks, rightclick on the RoadL layer and click on **Use Symbol Levels**. Inspect the results.
- 5. In the **Table Of Contents** section, right-click on the RoadL layer and navigate to **Properties** | **Symbology**. Uncheck the **<All other values>** value. Click on the **Advanced** button and select **Symbol Levels**.

6.	In Default View,	change the	order of symb	ols, as showr	n in the fol	lowing screenshot:
----	------------------	------------	---------------	---------------	--------------	--------------------

Sy	mbol Level	ls	the later	in intelli	-	X
[✓ Draw this	s layer using the symb	ol levels specified below			
	Symbol	Layer Name	Label	Join	Merge	Ŧ
		RoadL	Rural road			
		RoadL	Street			T
		RoadL	Field road			
		RoadL	Footpath			
						±
	<u>S</u> wite	ch to Advanced View			About s	ymbol levels
					ок	Cancel

- Click on **OK** twice to close the Layer Properties window. Inspect every bookmark to see the difference.
- 8. Return to the **Symbol Levels** dialog box and check the **Merge** column for Street and Field road.



- Click on **OK** twice to close the Layer Properties window. Inspect every bookmark to see the results.
- 10. Return to the **Symbol Levels** dialog box and change the view mode by clicking on the **Switch to Advanced View** button.
- 11. In the **Symbol** column, click on the down arrow to the right of every symbol to see the number of levels.
- 12. For column 1 (black layer), change the value: 0 for all symbols. For column 2 (colored layer), change the values to Footpath: 1, Field road: 2, Street: 3, and Rural road: 4. For column 3 (dashed line), change the value to 5.
- 13. Click on OK twice to close the Layer Properties window. Inspect the results.
- 14. Navigate to File | Save as and save your map document as MySymbolLevels.mxd at ...\Data\MapDocuments.

You can find the results at ...\Data\MapDocuments\Chapter5\SymbologLevelRoad. mxd.

How it works...

By selecting **Use Symbol Levels**, you resolved road intersections of the same type.

In **Default View**, you saw two options: **Join** and **Merge**. **Join** joined the same symbols that were intersecting each other on the map from the same feature class. **Merge** joined different symbols that were intersecting each other on the map.

In **Advanced View**, you saw the number of symbol layers for every symbol. The number indicates the order of drawing layers in ArcMap. Rural road has three symbol layers. The black layer has the drawing order 1, the colored layer has the drawing order 2, and the dashed line layer has the drawing order 3. This means that the black layer will be drawn first. All the other types of roads have only two symbol layers. Also, in **Advanced View**, there are three columns corresponding to the maximum number of layers identified in the feature class. The software is assigned by the default number to each symbol layer. These numbers define the order of drawing in ArcMap. The layers with the lowest number (0) draw first and the layers with highest number draw last (5). You changed the order of drawing at step 12. The Rural road will appear at the top of all other roads because it has the last two drawing orders (4 and 5).

-144

There's more...

If you want to resolve the gaps between the segments of the same feature type, you should change the Line cap type. Follow these steps to fill in the gaps:

- 1. In your map document, MySymbolLevels.mxd, open the Layer Properties and select the Symbology tab.
- 2. Open the **Symbol Property Editor** dialog for the Rural road subtype (click on the **Edit Symbol** button).
- 3. In the **Layers** panel, select every symbol layer, and for the **Line Caps** option, check **Round**. Click on **OK** to close all open dialogs.
- 4. Inspect the results. Save your map documents.

Using representation

In the previous recipes, you worked with traditional symbology. In this recipe, you will use advanced techniques to symbolize geographical features on a map. The representation allows you to solve different cartographic challenges, such as the overlapping of different symbols. With multiple representations for the same feature class, you can obtain different thematic maps displayed at different scales while needing only one feature class entry in the **Table Of Contents** section. The representations are the property of the feature class. In the previous sections, you depended on the .mxd or .lyr file to keep the symbology for a feature class on a map. Both types of files save the path to the physical store of the data and the way you choose to symbolize the features. Representations have rules and rules have one or more symbol layers. A representation is stored in the feature class and is managed by two fields: RuleID and Override.RuleID stores the rules for a representation. Override stores the exceptions from the rules. Rules define how it will be symbolized as a feature or a group of features (subtypes). Geometry overrides separate symbols to change or move the symbols in order to decongest an overfull map area.

Getting ready

You will convert the existing symbology to representation for three feature classes: Bridge, RoadL, and LandUse. Also, you will create your own representation marker named **Traffic Signal** and save it in TOPO5000.style.

145

How to do it...

Follow these steps to create cartographic representations for Bridge, RoadL, and LandUse:

- 2. In general, a representation of a feature class refers to a given scale. Please remember that your product will be a topographic map at the scale 1:5,000. That way, Representation.mxd has set 1:5,000 as the reference scale for the size of symbols or representations. The reference scale is a property of the data frame.
- 3. To define the reference scale for the data frame and symbols too, first type the scale 5000 in the Map Scale section. Second, right-click on the Layers data frame and navigate to Reference Scale | Set Reference Scale. Use Zoom in or Zoom out to see what happens to the size of the symbols. Notice that your symbol size relates to the display scale of the data frame. Symbols became smaller at small scales (for example, 1:15,000) and bigger at large scales (for example: 1:500).
- 4. To delete the reference scale for the data frame, in the Table Of Contents section, right-click on the Layers data frame and navigate to Reference Scale | Clear Reference Scale. Use Zoom in or Zoom out to see what happens to the size of the symbols without a reference scale for the data frame. Notice that your symbol size remains unchanged onscreen at different data frame scales.
- 5. Right-click on the **Bridge** layer and select **Create Symbology to Representation**. Accept the default parameters and uncheck **Add new layer to map symbolized with this representation**. Click on **Convert**.
- 6. In the **Table Of Contents** section, right-click on the **Bridge** layer and navigate to **Properties | Symbology | Representations**.
- 7. There are two sections: Rules and Layers. In the Rules section, there are three rules defined by the symbols of subtypes: Examine all the options, You can add or delete the rules, and You can modify every rule by adding more layer symbol (point, line, and polygon). You can change the graphic characteristics for all the existing layers. You can also control the Symbol Levels parameter if you click on the black arrow in the bottom-right corner of the Layers section.
- 8. To see the **Override field** section, select the **Fields** tab and check the **Override** parameter. Click on **OK**.
- 9. In the **Table Of Contents** section, right-click on the **Bridge** layer and select **Open Attribute Table**. Examine all the fields.


146

- 10. Repeat steps 6 to 8 for RoadL and LandUse layers.
- 11. You will create your own representation marker named My Traffic Signal using the **Marker Editor** tool. The zebra crossing will indicate the pedestrian crossing along the Rural road subtype feature.
- 12. In the **Table Of Contents** section, right-click on the RoadL layer and navigate to **Properties | Symbology | Representations**. Select the Rural road rule, and in the layers section, select the **Add new marker Layer** button, as shown in the following screenshot:

Layer Properties	1 1 1 1	×
General Source Select	ion Display Symbology Fiel	ds Definition Query Labels Joins & Relates Time HTML Popup
Show: Features	Draw using representatio	n stored in the layer's data source.
Categories Quantities	[1] <all other="" values=""></all>	xi <u>+</u>
Charts Multiple Attributes Representations RoadL_Rep	[2] Field road	Marker Marker:
	[3] Footpath	Angle: 0 Layers Clockwise: At extremities
	[4] Rural road [5] Street	Extremity: Just begin Position: 0 pt Angle to line:
	◎ ↑ ↓ × ▶	🥦 🇞 🕲 ↑ 🕹 × 📝 🗊 🕟
	Rules section	OK Cancel Apply

13. Select the default **Marker** (a black square), and in **Representation Marker Selector**, select **Square** from ESRI.style.





14. Select the **Properties** button and use the **Create Line** tool from **Marker Editor** to create a triangle with five vertical lines (zebra crossing), as shown in the following screenshot:


- 15. After you finish the symbol, click on OK. In Representation Marker Selector, save the custom symbol as MyZebraCrossing into TOPO5k.style in the ...\Data\ Representation folder. Select OK to return to the Layer Properties dialog. Zebra crossing has already been created in TOPO5k.style\Representation Markers.
- 16. Set Size to 8 pt for Zebra crossing marker into the Marker section. In the section Along line select black arrow from the right to open the Market Placements dialog. Navigate to the option Line input | At extremities and click on OK. For Extremity select Just begin. Click OK twice. Inspect the results in Data View.

In the upcoming steps, you will create a geometry effect to the hydrography:

- 17. Double-click on the LandUse layer to open the Layer Properties dialog. Navigate to Symbology | Representations and select the Hydrography rule. In the layers section select its Line layer and click on the Remove layer button from the bottom of the section to remove the line symbol layer.
- In the layers section, select the Solid color pattern layer and click on the black plus sign to open Geometric Effects. Navigate to Polygon input | Smooth and click on OK to return to Layer Properties.
- 19. Set **Flat tolerance** to 2 **pt** and click on **OK** twice. Inspect the Hydrography layer to see the results.



- 20. The **Smooth** effect doesn't influence the vertices or geometry. To check this, rightclick on the LandUse layer, and navigate to **Selection** | **Make This The Only Selectable Layer**.
- 21. From the **Editor** toolbar, start **Edit session**, and with the **Edit** tool, select the vector, and select the **Edit vertices** bottom. Visualize the river to see the difference. If you want to remove the smooth effect applied to the river feature in Data View, stop the Edit session and navigate to Layer **Properties | Symbology | Representation**. Select the **Hydrography** rule and click on the black arrow from **Smooth** section to select **Remove Effect**.
- 22. In the next steps, you will create overrides for River. Go to **Bookmark**, select **Overrides** to see the river section. The symbols of the road and river from LandUse layer are overlapped.
- 23. Start the edit session. Add the **Representation** toolbar by navigating to **Customize** | **Toolbars** | **Representation**. You will use the tools from the **Representation** toolbar.
- 24. With **Direct Select Tool**, select the river. All its vertices are selected. With the *Shift* key pressed, click again on the river to unselect all its vertices. With the *Shift* key pressed, select one by one the eight vertices from the overlapping river, as shown in the following screenshot:



25. Select **Warp Tool**, click on the corner of the road symbol, and drag-and-drop to reshape the edge as shown in the preceding screenshot.



- 26. The override doesn't influence the geometry of the feature from LandUse. To check this, select the river and click on the **Edit Vertices** tool to see the vertices of the polygon feature.
- 27. Save and stop the edit session. Save your map document as MyRepresentation. mxd at ... \Data\MapDocuments.

How it works...

Every time you create a representation for a feature class, a domain will be created in your file geodatabase. The domain controls representation rules from the **RuleID** field. The codes of the domain have the same values with the defined rules of representation. For example, the **Bridge** feature class uses the domain **Bridge_Rep_Rules** that has 4 values: **1** for **Bridge**, **2** for **Small wooden bridge**, **3** for **Unknown**, and **-1** for **Free Representation**.

In ArcMap, you can't convert, create, or modify cartographic representations in the edit mode (edit geometry of features). Instead, the overrides can be made during the edit session. When you have selected the river edge using **Select Tool** from the **Representation** toolbar, you have noticed that the selected representations look different than a selected feature using **Edit Tool** from the **Edit** toolbar. The reshaping of a representation doesn't influence the geometry of a feature. The shape or position of representation can be different from the original shape of the feature.

You can create, change, or delete the representations of the feature class in the ArcCatalog context menu or use the tools by navigating to **ArcToolbox | Cartography Tools | Representation Management**.

There's more...

The trees, thorny shrub, vineyard, and other marker symbols are cut off at the edge of the feature in LandUse. Follow these steps to resolve the problem marker symbols:


- 1. In the Table Of Contents section, double-click on the LandUse layer.
- 2. Click on [2] Forest Rule, select the first marker layer, and in the Inside Polygon section, go to Clipping, and select Whole markers cross boundary or No markers touch boundary.
- 3. Repeat the steps for every rule of the LandUse_Rep representation and see the changes in **Data View**.

However, still there is a problem: the trees symbol overlaps the Footpath subtype from RoadL. You will use **Free Representation** to isolate the marker symbol from **Forest rule** to change the position of each symbol. Follow these steps to use free representation to move the trees away from the footpath:

4. Start the **edit** session. From the **Representation** toolbar, click on **Select Tool**, and select the forest.



- 5. Navigate to Representation | Free Representation | Convert to Free Representation. Keep the forest selected. Navigate to Representation | Free Representation | Edit Free Representation. Please remember that Forest rule has two Marker layers: Coniferous and Deciduous.
- 6. With the **Select Part** tool from the right-hand side, select the whole forest.
- Select Marker (Coniferous), and with the Select Part tool activated, right-click on the selected forest and choose Separate Symbols Layers, as shown in the following screenshot:



- 8. Right-click again and choose **Convert Effect to Geometry**. Right-click again and choose **Explode Multi-part Geometry**. Now, you can select every coniferous tree from the forest. You can move or change the size of every tree individually.
- 9. Repeat steps 6 to 8 for the Deciduous tree symbol.
- 10. Click on OK to close the **Free Representation Editor** window. **Save** and stop the **edit** session. Save your map document.

See also

► For information about creating and working with labels for point, polyline, and polygon features on a map, please refer to the next chapter, *Building Better Maps*



6 Building Better Maps

In this chapter, we will cover the following topics:

- Creating and editing labels
- Labeling with Maplex Label Engine
- Creating and editing annotation
- Using annotation and masking for contours
- Creating a bivariate map

Introduction

In map design, a cartographer is not only thinking about the symbol of geographic feature but also its attributes. The descriptive text for features can vary in graphic characteristics in order to emphasize the differences, hierarchy, and importance of the features. The overall appearance and message of the map can be significantly affected by text characteristics, such as fonts, style (for example, italic, bold, and so on), character spacing, leading (space between lines in a block text), callouts and halos, fields used for labeling size, color, shape, position relative to the features, or display scale of the text. You can add descriptive text to your map using dynamic labels, annotations, and graphic text.

The dynamic labels are based on attribute values and are stored as a property of a layer in a map document, as a part of a map layer (.lyr), layer package (.lpk), or map package (.mpk). The dynamic labels are created using the **Standard Label Engine** or the **Maplex Label Engine**.

Building Better Maps -

The labels can be converted into annotations. The annotation makes your text editable (for example, font, size, position, text string, and so on). The annotation stores the text string, position, and display properties of the text. There are two types of annotations:

- Map document annotation (annotation group) stored in the map document (.mxd) as a property of the data frame
- Geodatabase annotation: standard annotation (not feature-linked) and feature-linked annotation

The graphic text is created for individual features using the **Text** tools from the **Draw** toolbar. The graphic text can be created based on the feature attribute but is not tied to the attribute value (for example, if the attribute is changed, the text is not updated). The graphic text is stored as a map annotation group in the map document.

In this chapter, you'll use advanced tools to create labels and annotations. In addition to this, you will display the height values with a visual effect for the contour lines. Finally, you will learn how to map quantitative data to create a bivariate map.

Creating and editing labels


When you are creating labels for an easy-to-read final map, you should do the following:

- Establish one or more attribute fields for labeling
- > Define the position of labels relative to the features its describes
- Define the position relative to other features or labels in order to minimize overlapping (for example, label weight ranking)
- Define the order of drawing labels on a map (for example, label priority ranking)
- Define the symbols for labels
- Create different label classes for the same feature class
- Avoid too many duplicate labels
- Add custom text to the labels if necessary
- Set a scale range (to control the display of the labels on the map) and work with the reference scale (to fix the size of the labels at a specific scale)
- Work with the Fast label quality (Labeling toolbar) to explore the preliminary results, and use the Best label quality for final labeling

154

Getting ready

In this recipe, you will use the **Draw** toolbar to add a graphic text for the TriangulationPoint feature class, and the **Labeling** toolbar to create dynamic labels for the Elevation and ContourLine feature classes, as shown in the following screenshot:



From the Labeling toolbar, you will work with Label Manager in the Standard Label Engine mode. The Label Manager dialog has two levels: feature class level and label class level. At the Feature Class level, you have two sections: Add label class and Add label classes from symbology categories. At the Label Class level, you have three main sections: Text String, Text Symbol, and Placement Properties. There are also three important buttons: Scale Range, SQL Query, and Label Styles.

How to do it...

Follow these steps to add a graphic text and dynamic labels:

- 1. Start ArcMap and open the existing map document, Label.mxd, from <drive>:\ PacktPublishing\Data\LabelingMaplex.
- 2. Load the **Draw** and **Labeling** toolbars. You will add text for a triangulation point feature from the TriangulationPoint layer using the **Rectangle Text** tool from the **Draw** toolbar, as shown in the preceding screenshot.



Building Better Maps -

- 3. Next to the point feature, draw a small rectangle. With the **Select Elements** tool from the **Tools** toolbar, right-click on the rectangle, and navigate to **Properties** | **Text**. In the **Text** section, type 8, create a new line using the *Enter* key, and type 242.59 on the second text line. Navigate to **Change Symbol** | **Style References**, add . . . \Data\TOPO5000.style to the **Symbol Selector** list. Select the **Geodetic Network** text symbol. At this point, you can modify the symbol properties and save it in TOPO5k.style with a different name.
- 4. Click on **OK** and on **Apply** to update the changes. Select the **Frame** tab and set **Border**: **None**. Click on **Apply**. Select the **Size** and **Position** tabs, and set **Width**: 90 and **Height**: 65. Click on **Apply** and on **OK** to return to **Data View**.
- 5. With the **Select Elements** tool, select and move the rectangle to the best placement from the cartographic point of view (for example, to the right-hand side of the point feature and slightly above the point).

In the next steps, you will create dynamic labels for the Elevation and ContourLine layers. From the **Labeling** toolbar, you will work with **Label Manager** in the **Standard Label Engine** mode, as shown in the following screenshot:

Label Manager	Labeling • X
Label Classes	Labeling 🕶 🚑 🖓 🆓 🆓 Kast 👻
	Text String Label Field: Elevation
Default P Default P Index contour line Intermediate contour line	Text Symbol A8c ■ ■ ■ ■ ■ ■ ■ ■ ■ ■ ■ ■ ■ ■ ■ ■ ■ ■ ■
	Placement Properties Orientation Horizontal Parallel On the line Curved Perpendicular Offset: 0 map units
Options <u> </u> <u> </u> <u></u>	OK Cancel Apply

156

The Label Manager dialog has two levels: feature class level and label class level. At the Feature Class level, you have two sections: the Add label class and Add label classes from symbology categories. At the Label Class level, you have three main sections: Text String, Text Symbol, and Placement Properties. The steps are explained as follows:

- 6. Open the Label Manager dialog, check Elevation from the left-hand side of the dialog, and select the Default label class. Click on Expression and create the following expression: FormatNumber([Elevation], 1). Click on Verify to check the expression, and click on OK. Click on Apply to update the settings and on OK to return to Data View. Inspect the results.
- 7. Return to the Label Manager dialog, check, and select the ContourLine feature class. In the Add label classes from the symbology categories section, there are five default label classes that correspond to the CNT (Type of contour line) subtypes filed. Keep checked only Index contour line and Intermediate contour line. Click on the Add button. Read carefully the warning message, and select No.
- 8. Every new label class inherits the characteristics of the Default label class. As the new label classes are created based on the subtypes, the groups are already defined in the **SQL Query** dialog.
- 9. Select the Default label class, click on SQL Query, and type the following expression: CNT <> 1 AND CNT <> 2. Click on Verify to check the expression. Click on OK. The Default label class will create labels for all subtypes except Index contour line (1) and Intermediate contour line (2).
- 10. Select the Index contour line label class and set the following parameters:
 - Label Field: Set this to Elevation
 - Text Symbol: Set this to Arial, 5 and Bold
 - Symbol: Set this to Elevation
 - Edit Symbol | Mask | Halo: Set the Size parameter 6 to 0.2 and Fill Color to White
 - Placement Properties | Orientation: Set this to Parallel
 - Placement Properties | Position: Set this to On the line
 - Properties | Duplicate Labels: Set this to Place one label per feature part
- 11. Accept the default settings for the remaining parameters. Click on OK.
- 12. Select the Intermediate contour line label class and repeat step 9, as shown in the preceding screenshot.



Building Better Maps -

13. Click on **Scale Range** to define the display range of the scale for the intermediate contour labels.

Because the precision of topographic datasets corresponding to the scale 1:5,000 and the intermediate contour are not labeled on a classical map, you will set a minimum and maximum scale to display the labels, as explained in the following steps:

- 14. Select **Don't show labels when zoomed**, and set **Out beyond**: 4990 and **In beyond**: 1000. Click on **OK** twice to close the dialog windows.
- 15. Explore the results. To fix the dimensions of the labels for the scale 1:5,000, select 1:5,000 on the Standard toolbar and right-click on the Layers data frame and navigate to Reference Scale | Set Reference Scale.
- 16. Use the **Lock Labels** and **View Unplaced Labels** options from the **Labeling** toolbar to fix the position of dynamic labels and see the unplaced labels.
- 17. Save your map as MyLabel.mxd at ... \Data\MapDocuments.

You can find the results at ... \Data\MapDocuments\Chapter6\LabelFinal.mxd.

How it works...

The graphic text created at step 3 is stored in the annotation default group as a property of the Topographic map 1:5,000 data frame by navigating to **View | Data Frame Properties | Annotation Groups.** If you lose or damage the .mxd file, your individual graphic text will be lost too. The dynamic labels created are the property of the Elevation and ContourLine layers and can be stored in the Label.mxd map document or the .lyr file.

FormatNumber() is a VBScript function that returns a number. This function has one required parameter (expression) and four optional parameters. You used only the first optional parameter named NumDigAfterDec to define one decimal place for the numeric number format.

For the ContourLine layer, you have to use label classes to create three different label styles for three different groups of features.

A common mistake is to forget to define the group of features that will be labeled by the label classes.

If you want to see the mask of labels, in the **Table Of Contents** section, right-click on the **Layers** data frame, navigate to **Properties** | **Data Frame** | **Background**, and select a color.



See also

► To learn how to better control the dynamic labels using **Maplex Label Engine**, please refer to the next Labeling with Maplex Label Engine recipe

Labeling with Maplex Label Engine

In the previous recipe, you worked with the **Standard Label Engine** parameter. In this recipe, you will use the **Maplex Label Engine** parameter to create high-quality dynamic labels. The dynamic labels will be placed and oriented on the map based on criteria such as best fitting, density, or priority and weight rankings for features and labels that are overlapping.

The **Maplex Label Engine** parameter allows you to control the displayed text of the label using the **Abbreviation Dictionary** tool.

There are three types of abbreviations:

- ► **Translation**: The value of the label will be replaced with a custom one; the abbreviation is used whether there is space or not to display the label (for example, A can be used in place of Arable).
- Keyword: This will return an acronym formed by the first letter of each word from the label; the abbreviation is used only if there is not enough space to display the label (for example, DA in place of Dwelling Annex or GSG in place of Gibson Square Gardens).
- Ending: This abbreviates the last word from the label; the abbreviation is used only if there is not enough space to display the full label (for example, Oldhill St in place of Oldhill Street).


For instance, you can use the **Abbreviation Dictionary** tool to translate the label values into another language without changing the structure of the attribute table or field values.

159


Building Better Maps

Getting ready

In this recipe, you will create labels corresponding to a topographic map at the scale of 1:5,000 for the LandUse feature class, and labels corresponding to a cadastral map at the scale 1:500 for the Buildings feature class, as shown in the following screenshot:



The following screenshot describes the structure of the Dwelling label class according with the cadastral map label style:



How to do it...

Follow these steps to create dynamic labels using the Maplex Label Engine parameter:

 Start ArcMap and open the existing map document Maplex.mxd from <drive>:\ PacktPublishing\Data\LabelingMaplex.



- Load the Labeling toolbar. From the Labeling toolbar, navigate to Labeling Use | Maplex Label Engine.
- 3. In the next steps, you will define and add abbreviations for the coded values of the LandUse: CAT (Category) and Buildings: CDC (Destination) fields.
- Navigate to Labeling | Abbreviation Dictionaries. Select New and type MyLandUse. Select Add Row and for the new empty row, set the following: Keyword: 0, Abbreviation(s): Unk, and Type: Translation.
- 5. Navigate to **Options** | **Append From File** and select the existing dictionary file LandUse.dic from ...\Data\LabelingMaplex. Click on **Open**. Now you have abbreviations for every subtype from the CAT (Category) subtype field.
- 6. Let's add the second dictionary for the Buildings layer. Select in Options: Open From File and load the existing dictionary file Building.dic from ...\Data\ LabelingMaplex. Click on Open. Select Rename and type MyBuilding. Click on OK twice to close the dialog windows and return to Data View.
- 7. Open the **Label Manager** dialog, and check the Buildings and LandUse feature classes.
- 8. Select LandUse and for **Select symbology categories**, uncheck all symbology categories except Hydrography and Transportation. Click on the **Add** button. Read carefully the warning message, select **No** to keep the Default label class, and add the two additional classes.
- 9. Check and select the LandUse: Default label class, and set Label Field: CAT (Category). For Text Symbol, select Symbol, and choose the LandUse symbol from ...\Data\TOPO5000.style. Click on OK.
- 10. To exclude the Hydrography and Transportation features from being labeled with the Default label class, click on SQL Query and build the following expression: CAT <> 31 OR CAT <> 41. Uncheck Display coded value description to work with the coded value on your map. Click on Apply to update the settings in your map.
- 11. In the **Placement Properties** section, select **Position**: **Horizontal** and **Land Parcel Placement** to add horizontal labels that will not overlap the buildings inside the parcel polygons. Click on **OK**.
- 12. Select **Properties** to open the **Placement Properties** dialog. Click on the **Fitting Strategy** tab and check **Reduce font size**. Check **Abbreviate label**, select **Options**, and choose the MyLandUse dictionary name to replace the coded values of the CAT (Category) subtype field with the custom abbreviations. Click on **OK**.
- 13. Click on the **Strategy Order** button, use black arrows to add the **Abbreviate** label at the top and **Reduce font size** in second place. Click on **OK**.



Building Better Maps -

- 14. Click on the Label Density tab, navigate to Minimum feature size for labeling | Area, and set 2000 Map Units. Explore the remaining tabs to see all the Maplex advanced options. Return to the Label Manager dialog box. Select Scale Range and check Don't show labels when zoomed. Type 10001 in the Out beyond section and 100 in the In beyond section. For this scale range, the parcel labels will be displayed on your map. Click on Apply.
- 15. Check and select the LandUse: Hydrography label class. Click on **Expression** and uncheck **Display coded value description**. Navigate to **Text Symbol** | **Symbol** and choose the **Stream** symbol from TOPO5000.style. Click on **OK**.
- 16. In the **Placement Properties** section, select **River Placement** with **Position**: Curved. For **Properties**, set the following parameters:
 - Fitting Strategy | Abbreviate label: MyLandUse
 - **Conflict Resolution**: Never remove
- 17. Click on **OK** and on **Apply**.
- 18. Uncheck the LandUse: Transportation label class. You will not add labels for roads, but you will use this label class later in this exercise to constrain the Dwelling label class to overlap with road features.
- 19. Select Buildings and for **Select symbology categories**, uncheck all symbology categories except the Dwelling category. Click on **Add** and on **No** for the warning message.
- 20. Check and select the Building : Default label class and set Label Field: CDC (Destination). Uncheck Display coded value description to work with the coded value on your map. Click on OK.
- 21. For **Text Symbol**, select **Symbol**, and choose the Building symbol from TOPO5000. style. Click on **OK**.
- 22. To exclude the Dwelling features to be labeled with the Default label class, click on the SQL Query parameter, and build the following expression: CAT <> 1. Click on Apply.
- 23. In the **Placement Properties** section, select **Position**: **Horizontal** and **Regular Placement**. For **Properties**, set the following parameters:
 - Fitting Strategy: Reduce font size
 - **Abbreviate label**: MyBuilding.
 - Strategy Order: first place Abbreviate label, and second place Reduce label in size
- 24. Return to the Label Manager dialog. Navigate to Scale Range | Don't show labels when zoomed, and set Out beyond: 5000 and In beyond: <None>. The labels will be displayed starting from the scale 1:5,000 and larger (for example: 1:500). Click on OK.

- 162

- 25. Check and select the Building: Dwelling label class, navigate to Label Field | Expression | Load, and choose the BuildingLabel500.lxp expression file from ...\Data\LabelingMaplex. Uncheck Display coded value description.
- 26. Click on Verify to check the expression and click on OK.
- 27. Navigate to **Text Symbol** | **Symbol**, and set **Placement Properties** parameters as shown for the Building parameter in the Default label class. For the Building parameter in the Dwelling label class, do not check **Abbreviate label**.
- 28. Navigate to Scale Range | Don't show labels when zoomed, and set Out beyond: 1000 and In beyond: 100. Click on OK.
- 29. In the **Label Manager** dialog box, click on **Apply** and on **OK**. It may take several seconds for the labels to be placed.
- 30. Set the reference scale for the labels at 1:500. To see and analyze the position and dimensions of the labels, navigate to Labeling | Lock Labels, and use the View Unplaced Labels tools. The position of the labels should be locked and the unplaced labels displayed in red.
- 31. From the **Labeling** toolbar, set the **Label Priority Ranking** and **Label Weight Ranking** parameters, as shown in the following screenshot:

	~				
Label Priority Ranking	1				
Label Priority					
Rank label classes in priority order: Labels at the top of the list have the highest priority.		Weight Ranking	_		x
Buildings - Dwelling Buildings - Default LandUse - Default		Weights let you control which labels will be placed when the	nere are potential conflicts (ov	erlaps)	
LandUse - Hydrography LandUse - Transportation		Feature Layer - Labeling Class	Feature Weight (Range 0 to 1000)	Polygon Boundary Weight	î
↓		Buildings - Default	1	1	
		Buildings - Dwelling	1	1	
±		LandUse - Default	1	1	
		LandUse - Hydrography	1000	1000	
Tip: Hold down SHIFT or CTRL to select multiple label classes.		LandUse - Transportation	1000	1000	
OK Cancel Apply		Double-click on column header to sort table. Show: Feature Layers	• OK	Cancel Apply	·

The value 1000 for Hydrography and Transportation means that no labels will be placed on the river and road polygons. The value 1 for Buildings tells the **Land Parcel Placement** style (from step 10) to avoid placing the parcel labels on any polygon features (buildings) inside the parcel polygons.

- 32. Clear the reference scale for your data frame, and explore the results on the map using the **Pan**, **Zoom In**, and **Zoom Out** tools.
- 33. Return to **Label Weight Ranking** and set the **Transportation** parameter to 0. Notice how dwelling labels are drawn on the road now.
- 34. Save your map as MyMaplex.mxd at ... \Data\MapDocuments.

You can find the results at ... \Data\MapDocuments\Chapter6\MaplexFinal.mxd.



Building Better Maps

How it works...

You worked with two abbreviation dictionaries that renamed your subtype codes from the Buildings and LandUse feature classes without changing the values in attribute fields.

When you use **Label Priority Ranking**, you define which label classes have higher priority and which have lower priority in displaying on the map. When you use **Label Weight Ranking**, you define the label position relative to other features or labels in order to minimize overlapping in displaying on the map.

Priority and weight ranking influences the labeling speed because the ArcMap label engine evaluates the location of features before placing the labels, and based on label conflict detection and space availability, labels are rearranged every time you use **Full Extend**, **Pan**, **Zoom In**, and **Zoom Out**.

There's more...

As you might have already noticed, some labels are too small to read clearly, especially for dwellings. Go to the Windows menu and select **Magnifier** to see your labels at different scales. Explore the results on the map using your magnifier window. You can change the zoom, or you can set a specific scale by selecting the black arrow from the right-hand side of the **Magnifier** window. Select **Properties** and make your own changes. Also, you can add more magnifier windows.

Creating and editing annotation

In this recipe, you will convert your high-quality, dynamic labels created with **Maplex Label Engine** into a geodatabase annotation feature class. A geodatabase annotation feature class is another type of feature class stored in a feature dataset inside the geodatabase. There are two types of annotation feature classes:

- Not feature-linked annotation feature class (standard)
 - They are stored as independent pieces of text
 - Only if text has been derived from the attributes of a feature, annotations are not tied to the attribute value (if the attribute value is changed, the text is not updated)
 - If you move or erase a feature, the annotation will remain the same
- Feature-linked annotation feature class
 - They are generated based on feature attributes




- It is a composite relationship class with 1-M cardinality between a feature class as the origin table and an annotation feature class as the destination table, using the **OBJECTID** field as the primary key and the **FeatureID** field as the foreign key
- □ If you move a feature, the annotation will move with the feature
- Let If you erase a feature, the annotation will be erased too
- If you change the attribute value for a feature, the feature-linked annotation text will be changed

Getting ready

Firstly, you will improve the position of labels for Elevation and ContourLine using **Maplex Label Engine**. After that, you will create a standard annotation feature class and two feature-linked annotation feature classes for the reference scale 1:5,000.

For the Buildings feature class, you will create a feature-linked annotation feature class for the reference scale 1:500, as shown in the following screenshot:



In the last part, you will edit the annotation features to correct the position, dimension, and other graphic characteristics of the annotation text.

165

Building Better Maps -

How to do it...

Follow these steps to convert dynamic labels to geodatabase annotations:

- Start ArcMap and open the existing map document Annotation.mxd from <drive>:\PacktPublishing\Data\Annotation.
- Load the Labeling toolbar and check whether the Use Maplex Label Engine option is selected. Open Label Manager and set the Elevation parameter to the Default label class for the feature class. In the Placement Properties section, set Position as Best Position. Navigate to Properties | Conflict Resolution, and check Background Label (placed first) and Never remove (place overlapping). Click on OK and on Apply.
- 3. For the ContourLine layer, right-click on the Default label class, and select **Delete Class**. Delete also the Intermediate label class. Select the Index contour line label class and navigate to **Placement Properties** | **Contour Placement**. Navigate to **Properties** | **Label Position** | **Options**, and check **Uphill alignment** and **No Laddering**. Click on **OK**.

Using the **Uphill alignment** option, you will label contour lines in accordance with topographic principles about the representation of landforms and terrain features by contours.

- 4. For Label Density, check Repeat label, and select its Options. Set Minimum Repetition Interval: 1000 Map Units to have a reasonable density of labels per contour line for a topographic map at the scale 1:5,000. For Conflict Resolution, check Never Remove (place overlapping). Click on OK to return to the Label Manager dialog window and click on Apply.
- 5. Inspect the remaining label classes. Click on **OK** to close the **Label Manager** option.
- 6. Select the Pan tool and drag the map to redraw the position of labels in the Label to Annotation data frame. Even if it slows down the drawing of the dynamic labels, set the placement quality to Best (the Labeling toolbar). Check the Label Weight Ranking parameter to see that LandUse is set to Transportation and Hydrography. Set Feature Weight of 1000 to constrain the labels not to be placed on the road or river polygons.

Before converting dynamic labels to annotations, you have to define the reference scale for the annotation. An annotation uses the reference scale for the current data frame. If the reference scale for the data frame is not defined, the annotation will use the display scale of the current data frame by navigating to **Standard | Map Scale** and set it to 5000 before converting labels to annotations. Let's create a standard annotation feature class by performing the following steps:



 Set the reference scale for the data frame to the scale 1:5,000. In the Table Of Contents section, right-click on the Elevation layer, and select Convert Labels to Annotation. Set the parameters, as shown in the following screenshot:

Store Annotation	⊚ In the <u>m</u> ap		Reference Scale	000
Create Annotation For	© <u>F</u> eatures in c	current extent	Selected feat	atures
Feature Layer	Feature Linked	Append	Annotation Feat	ure Class
Elevation			ElevationAnnotation	🖆 🖆
	unchecked	3DAnal Annota CRS Design Editing Exporti Geocoo	lyst 🔂 Labi ition 🔂 Line ingGeodatabase 🔄 Rep Data 🔤 Spat ngMaps 📑 TOF	elingMaplex arReferencing Documents resentation iialAnalyst OS000.gdb
Destination: TOPO50	00.gdb\Relief\El	evation.Annota	ation	

Because of the overlapping conflicts, some labels will be hidden. The **Convert unplaced labels to unplaced annotation** option will transform the unplaced labels too. The **In the map** option means that your annotation will be stored as Annotation Group associated to the Elevation layer. The annotation will be stored in the map document (.mxd) as a property of your current data frame.

8. Click on **Convert**. The ElevationAnnotation layer has been automatically added in the **Table Of Contents** section. Notice that dynamic labels of the Elevation layer have been deactivated in **Label Manager**.

167—

Building Better Maps -

Let's create three feature-linked annotations for the ContourLine, LandUse, and Buildings layers, as shown in the following screenshot:

Convert Labels to Annotation	
Store Annotation Reference Scale Image: Image	□ Results_TOPO5000.gdb □ □ Buildings □ □ Anno 174_197 □ □ Buildings reference scale 1:500
Create Annotation For	BuildingsAnnotation LandUse Anno_175_195 M LandUse andUse annotation
Feature Layer Feature Linked Append Annotation Feature Class ContourLine Image: ContourLine Annotation Image: ContourLine Annotation Image: ContourLine Annotation	Relief
Destination: TOPO5000.gdb\Relief\ContourLineAnno	ContourLine ContourLineAnnotation Elevation ElevationAnno standard annotation
<u>Convert</u> unplaced labels to unplaced annotation <u>Convert</u> <u>Cancel</u>	standard annotation

- 9. For the Buildings layer, set the reference scale to 1:500. After you create the 1:500 annotation for the Buildings layer, navigate to **Reference Scale** | **Clear Reference Scale**.
- 10. Now, you have four annotation feature classes. Explore the results in **Data View** using the **Zoom In**, **Zoom Out**, and **Pan** tools.

In the next steps, you will change the position and the size of one dwelling annotation from the BuildingsAnnotation layer:

- 11. Start the editing session. By default, you have the **Edit Annotation Tool** parameter on the **Editor** toolbar. To add more annotation tools, click on the drop-down arrow from the right-hand side of the **Editor** toolbar, and select **Customize**. Select **Commands** and for **Show commands containing**, type anno. Click and drag the **Unplaced Annotation** and **Construct Annotation with A Leader Line** tools to the **Editor** toolbar. Click on **Close**.
- 12. Click on the **Unplaced Annotation Window** tool and in the **Show** section, select BuildingsAnnotation as the Dwelling annotation class.

The **Unplaced Annotation** window shows three columns: **Text**, **Class** (annotation class), and **FID Linked** (the OBJECTID value of the linked dwelling feature that is related to the annotation feature).

13. Uncheck Visible Extent and check Draw to see the unplaced annotations in a red outline rectangular. Click on Search Now and right-click on the first unplaced annotation to choose Zoom to Feature. Right-click again on the selected annotation and choose Place Annotation to change the annotation status as Placed, as shown in the following screenshot:

A ² s,fb 7	6 m ² 1 -	_	± 中 X २।□ ✓		
Unplaced Annotation					□×
Show: Dwelling	•	Search Now	Visible Extent	🔽 Draw	
Text		Class		FID Linked	-
A ² _s	IRs fh 76 m <slips2< s<="" td=""><td>Ruildings∆n</td><td>optation : Dwelling</td><td>6</td><td>=</td></slips2<>	Ruildings∆n	optation : Dwelling	6	=
A ² _{s<!--</td--><td>Place Annotation</td><td>Space</td><td>station : Dwelling</td><td>8</td><td></td>}	Place Annotation	Space	station : Dwelling	8	
B ² _{<td>Pan to Annotation</td><td>р</td><td>station : Dwelling</td><td>16</td><td></td>}	Pan to Annotation	р	station : Dwelling	16	
A ² _{s<!--</td--><td></td><td>_ `</td><td>tation : Dwelling</td><td>18</td><td></td>}		_ `	tation : Dwelling	18	
D ¹ _{<!--</td--><td>Zoom to Annotation</td><td>n Z</td><td>tation : Dwelling</td><td>19</td><td></td>}	Zoom to Annotation	n Z	tation : Dwelling	19	
D-30F/15/30F/30D/3/					
D ¹ _{s<!--</td--><td>Pan to Feature</td><td></td><td>itation : Dwelling</td><td>21</td><td></td>}	Pan to Feature		itation : Dwelling	21	
			tation : Dwelling tation : Dwelling	21 23	
D ¹ _{s<!--</td--><td>Pan to Feature Zoom to Feature</td><td></td><td>-</td><td></td><td></td>}	Pan to Feature Zoom to Feature		-		


14. Your annotation list can be slightly different. You can set the **Placed** status for unplaced annotations in the BuildingsAnnotation attribute table. The status is stored in the **Status** field that has assigned the AnnotationStatus domain.

In the next steps, you will edit the annotation, as shown in the upcoming screenshot:

- 15. Select the previous annotation with the Edit Annotation Tool parameter and click on the Attributes button. In the Attributes dialog, click on the Expand All Relationships In Branch button. Explore the attribute fields of the annotation feature and the related-dwelling feature from the Buildings feature class.
- 16. Select the related building feature and change the Stories value to 10. The text from the annotation feature class is immediately updated because the annotation is linked to the dwelling feature.

Building Better Maps -

17. Select the annotation feature and click on the Annotation tab. Split the single text line into three different lines. Select the Leader button and choose Simple Line Callout. Click on OK and on Apply. Select the annotation and move outside the polygon boundary to see the leader line.




Let's add a new annotation to your building. To quickly view the OBJECTID value from the Buildings layer, navigate to its Layer Properties | Display and set Field: OBJECTID and Show MapTips using the display expression.

18. From the Editor toolbar, select the Create Features tool. Set

BuildingsAnnotation as the AB Dwelling feature, choose **Construction Tools**, and set it as the **Leader** tool. In the **Annotation Construction** window, type demolished in 2012. Your mouse pointer has a small cross with the custom text. Click your pointer on the building to create the annotation as shown in the following screenshot:

Chapter 6



19. To create a feature-linked annotation, you have to edit the FeatureID field with the building OBJECTID value. Save the edit by navigating to **Editor** | **Save Edits**.

Let's test the relationship between the Buildings and BuildingsAnnotation layers, as follows:

- 20. With the **Edit** tool, select and right-click on the related building and choose **Delete**. The buildings and the two related annotations from BuildingsAnnotation will be erased too.
- 21. Undo the last action by navigating to the **Standard** toolbar | **Undo Delete Feature** tool. Select the building and move to a new location. The two related annotations will be moved too.
- 22. Save your map as MyAnnotations.mxd at ... \Data \MapDocuments.

You can find the results at ... \Data\MapDocuments\Chapter6\AnnotationFinal.mxd.

How it works...

If you have two data frames in a map document and erase one of them, you will lose all map annotation groups that are associated with that data frame. If you save the labels in the map document as an annotation group, the unplaced dynamic labels will be reported as **Overflow Annotation**. To keep an overflow annotation in a map document, right-click on the annotation, and choose **Add Annotation**.

171-

Building Better Maps -

While converting labels to the annotation feature class, the annotation is automatically added in the **Table Of Contents** section. Notice that all annotations (standard or feature-linked) have annotation classes created from the label classes. These annotation classes are stored in the geodatabase as subtypes in the AnnotationClassID subtype field. Examine in ArcCatalog the properties of the standard and feature-linked annotation feature classes you just created.

If you made a mistake, you can erase the existing annotation class and create another one. You can also create many annotation feature classes for the same feature class. This can be useful if you are creating different thematic maps at different scales for the same dataset. If you decide to combine all annotation feature classes in one, you will have two options: check **Append** from the **Convert Labels to Annotation** dialog, or use the **Append Annotation Feature Classes** tool by navigating to **ArcToolbox | Data Management Tools | Feature Class**.



An annotation created from standard dynamic labels cannot combine with an annotation created with Maplex Label Engine. Both annotations must use labels that are created with the same label engine. Two feature-linked annotation feature classes created for the same feature class can be combined in a single one. A new, empty annotation feature class can be created with ArcCatalog, at the geodatabase level or the feature dataset level and edited in ArcMap.

The annotation feature class is stored as a polygon feature class. The polygon representing the outline of the annotation can be resized, rotated, flipped, curved (edit the **Base Line Sketch** parameter), and converted into multiple parts. The curve annotation has vertices that can be deleted, added, or moved. To make all these changes, select annotation, and right-click to choose the edit options.

There's more...

You might have noticed in the **Table Of Contents** section a new symbol on the left-hand side of the annotation classes when you use **Zoom In** or **Zoom Out**. This square with a double base indicates that the annotation class will not be drawn because it is out of the scale range already defined for the dynamic label class and inherited by the annotation class. You can change this restriction by right-clicking on the annotation class and selecting the **Visible Scale Range** parameter.

See also

Explore the ContourLineAnnotation layer with the Magnifier tool at the reference scale of 1:5,000. There are some values with small segments between the digits. To learn how to use annotation in this cartographic issue, please refer to the next Using annotation and masking for contours recipe.


172

Using annotation and masking for contours

According to the commonly used rules in a topographic map, all contour lines should be interrupted beneath the elevation information. In this recipe, you will learn how to use the geodatabase annotation to display the elevation value with a visual effect for contours.

Getting ready

In this section, you will display on a topographic map at the scale of 1:5,000 the elevation value for the contour lines and elevation points as shown in the following screenshot:



Firstly, you will create an annotation feature class that stores the point and index contour line elevation. Secondly, you will use the **Feature Outline Masks** tool by navigating to **ArcToolbox** | **Cartography Tools** | **Masking Tools** to obtain an intermediary polygon feature class that contains the mask (a polygon created around the text) for the annotations. Finally, based on the mask layer, you will create a visual discontinuity for index contour lines in accordance with the position of the annotation for contour lines and elevation points.

Building Better Maps -

How to do it...

Follow these steps to create labels for contour lines and elevation points:

- 1. Start ArcMap and open the existing map document AnnoMaskAdvancedDraw.mxd from <drive>:\PacktPublishing\Data\Annotation.
- 2. Navigate to the **Labeling** | **Label Manager** dialog box. Inspect the label settings for the Elevation and ContourLine layers.
- 3. Uncheck the white halo for the ContourLine: Index contour line label class by navigating to **Text Symbol | Symbol | Edit Symbol | Mask** and set it to None. Keep clicking on **OK** until all the dialog windows are closed.
- 4. To analyze the position and dimensions of the labels, navigate to Reference Scale | Set Reference Scale, and set it to 1:5,000 for the current data frame. Then navigate to the Labeling | Lock Labels tool to hold the convenient position of the displayed labels.

Let's create a single standard annotation called ElevationContourAnnotation that will store the annotation features for both the Elevation and ContourLine layers by performing the following steps:

5. Right-click on the Elevation layer and select **Convert Labels to Annotation**. Set the parameters, as shown in the following screenshot:

Convert Labels to Annotatio	n		X			
Store Annotation			Reference Scale			
In a <u>d</u> atabase (C)) In the <u>m</u> ap		1:5,000			
Create Annotation For						
All features (C)) <u>F</u> eatures in c	current extent	Selected features			
Feature Layer	Feature Linked	Append	Annotation Feature Class			
Elevation			ElevationContourAnnotati 👩 🚰			
Destination: TOPO5000.gdb\Relief\ElevationContourAnnotation						
Convert unplaced label	Destination: TOPO5000.gdb\Relief\ElevationContourAnnotation Image: Convert unplaced labels to unplaced annotation Convert Cancel					



6. Click on **Convert**. Right-click on the ContourLine layer and select **Convert Labels to Annotation**. Set the parameters, as shown in the following screenshot:

Cor	nvert Labels to Annotatio	n			x		
	Store Annotation In a <u>d</u>atabase) In the <u>m</u> ap		Reference Scale 1:5,000			
	Create Annotation For <u>A</u> II features) <u>F</u> eatures in o	current extent	Selected features			
	Feature Layer	Feature Linked	Append	Annotation Feature Class	Â		
	ContourLine		V	ElevationContourAnnotation 🔗			
	Destination: TOPO5000.gdb\Relief\ElevationContourAnnotation Image: Convert unplaced labels to unplaced annotation Convert Cancel						

- 7. Check the **Append** option to store the annotation features in the existing ElevationContourAnnotation geodatabase annotation. Click on **Convert**.
- 8. Check and correct the position of the annotations in **Data View** if it's necessary.
- 9. Open **ArcToolbox** and navigate to **Cartography Tools** | **Masking Tools**. Double-click on the **Feature Outline Masks** parameter, and set the following parameters:
 - Input layer: ElevationContourAnnotation
 - Output Feature Class: TOPO5000.gdb\Relief\Mask
 - Margin (optional): 2.5 Meters
- 10. Leave unchanged the remaining default options. Click on **OK**.
- 11. In the **Table Of Contents** section, turn off the Mask layer. Right-click on the current **Layers** data frame and select **Advanced Drawing Options**. Check **Draw** using specified masking options. For **Masking Layers**: Mask, check **Masked Layers**: ContourLine. For **Masking Layers**: WatercourseA, check **Masked Layers**: WatercourseL. Click on **Apply** and on **OK**.
- 12. Explore the results. Save your map as MyMaskAnnotations.mxd at ... \Data \ MapDocuments.

You can find the results at ... \Data\MapDocuments\Chapter6\ AnnoMaskAdvancedDrawFinal.mxd.



Building Better Maps -

How it works...

When an ElevationContourAnnotation feature annotation is moved, the corresponding feature from Mask will not automatically move. You have to move the polygon mask to align with the annotation feature. The **Advanced Drawing Options** parameter is the property of data frame, and for this reason, you have to keep the mask layer in the current data frame from your map document (.mxd file). Saving the ContourLine as a layer file doesn't help to keep the visual effect for contour line features.

Creating a bivariate map

In this recipe, you will display two quantitative attributes of a single feature class. The result of displaying two attributes at the same time for a polygon feature class is called a **bivariate map**.

Getting ready

In this section, you will use the Census feature class to create a quantitative bivariate map that analyzes two variables from the census data: NoEducation (number of persons with no education) and Unemployment (unemployment rate).

How to do it...

Follow these steps to create a bivariate map using the **Quantity by Category** option:

- Start ArcMap and open a new map document. In the Table Of Contents section, rightclick on the data frame called Layers, select New Group Layer, rename it by selecting the new group layer, and type Multiple Attributes/Quantity by category.
- 2. Right-click on the group layer and select **Add Data**. Load the Census2010 feature class from ...\Data\TOPO5000.gdb\Boundaries.
- 3. To display only the subset of features that have the census information, right-click on the Census layer, and navigate to **Properties** | **Definition Query** | **Query Builder**. Build the following expression: PopulationOver10 <> 0. Click on Apply.
- 4. Click on the Symbology tab and navigate to Multiple Attributes | Quantity by category. In the Value Fields section, select the first field Unemployment and the second field NoEducation. Click on the Add All Values tab and uncheck the <All other values> option.

-176

Let's group the **Values** option in four classes based on the Unemployment field values, as follows:

5. Select all values **4** (**4**, **18166**; **4**, **13173**; **4**, **13879**; **4**, **8462**), right-click on the selected values, and choose **Group Values**, as shown in the following screenshot:


Layer Properties		×
General Source Selecti Show: Features Categories Quantities Charts Multiple Attributes Quantity by category	ion Display Symbology Fields Draw quantities for each cate Value Fields Unemployment NoEducation none	Definition Query Labels Joins & Relates Time HTML Popup agory. Import Color Scheme Variation by Color Ramp Symbol Size
	Symbol Value <all other="" values=""> <heading> 4, 18166 4, 13173 4, 13879 4, 8462 5, 11438 6 6 6 7, 1438 6 6 7, 1438 6 6 7, 1438 6 7, 1438 7,</heading></all>	Label Count <all other="" values=""> 0 Upcomploament No Ect or 12 4 Group Values 4 Ungroup Values 4 Reverse Sorting 5 Remove Value(s) 6 Flip Symbols 9 Properties for Selected Symbol(s) 9 Apply Color Scheme 2 Edit Description</all>
		OK Cancel Apply

- 6. Repeat step 5 to group values **5**, **6** and (**7-8**). You obtained four new classes. Click on **Apply**. Set **Color Scheme**: Errors color ramp and click on the **Value** field to choose **Reverse Sorting**.
- 7. Navigate to Variation by | Color Ramp. Set Value: NoEducation, navigate to Classification | Natural Breaks (Jenks) | Classes, and set it to 4. Click on OK. For Color Ramp, choose Cyan-Light to Blue-Dark. On the Value field, click on and choose Reverse Sorting. On the Symbol field, click on and choose Flip Symbols.
- 8. Click on **OK** to close the dialog box and on **Apply** to see the updates in **Data View**. Edit **<Heading> Label**: Unemployment/NoEducation. Click on **Apply** and on **OK**.



Building Better Maps -

- Navigate to View menu | Layout View to add a legend for your bivariate map. Navigate to Insert menu | Legend. In the Legend Wizard dialog window, set the following parameters:
 - Set the number of columns in your legend: 4
 - Legend Title: erase the text and leave empty
 - Patch Width: 30; Patch height: 30
 - Columns: 0; Patches (vertically): 0
- The Legend option generated on your map doesn't look good. Right-click on the Legend option, and navigate to Properties | Items tab | Style button | Legend Item Selector. Select the Horizontal Single Symbol Description Only parameter, and click on OK. Click on Apply to see the legend updates.
- 11. Select the **Layout** tab and check the **Right to left reading** option to switch the matrix. Click on **Apply** to see the matrix update. Click on **OK** to return to **Layout View**.
- 12. You can insert text by navigating to **Insert menu** | **Text** to describe the two axes, as shown in the following screenshot:



-178

13. Navigate to Standard toolbar | Select Element to select the text or legend elements. Explore the results. Save your map as MyBivariateMap.mxd at ... \Data\ MapDocuments.

You can find the results at ... \Data\MapDocuments\Chapter6\BivariateMap.mxd.

How it works...

You grouped the displayed features in four categories of unemployment rates (7-8 percent, 6 percent, 5 percent, and 4 percent). Every category of unemployment rate groups the number of persons with no education into four quantitative classes based on the natural grouping of NoEducation field values. Based on the sixteen groups, you created a legend color matrix with four rows and four columns.

The four categories of unemployment rate are symbolized by the Error ramp scheme.

The four quantitative classes representing the number of persons with no education are symbolized with the Cyan-Light to Blue-Dark color ramp (step 7).

The **Quantity by category** classification creates the final symbol, that of colors, by keeping the Hue from the first symbology (Error ramp scheme) and adds Saturation and Value from the secondary symbology (Cyan-Light to Blue-Dark). You can check this using the **Eye Dropper** tool and the **Color Selector** tool (RGB and HSV color space).

See also

► For more information about working in **Layout View**, please refer to *Chapter 7*, *Exporting Your Maps*



In this chapter, we will cover the following topics:

- Creating a map layout
- ► Exporting your map to the PDF and GeoTIFF formats
- Creating an atlas of maps
- Publishing maps on the Internet

Introduction

Before we start creating a map or a poster containing a map body, think about the following aspects that can influence your final product:

- Audience (for example, the technical team)
- Objectives (for example, the topographic map)
- ▶ Map scale (for example, 1:2,000)
- Visual balance (for example, the main map body as a central theme of the map)
- Technical limits (for example, printer map size)

In the next four recipes, you will design, prepare, and export a map. You will share the contents of the map with your colleagues using a map package format through the **ArcGIS Online** platform. You can find the results of this chapter at <drive>:\PacktPublishing\Data\ExportingMaps\MyResults.

Creating a map layout

A **map layout** is a final map product created in **Layout View** that can be shared with other users. A map layout is designed for digital view or print. **Layout View** is the map design environment in ArcGIS.

The main map elements are map body, graticule, scale bar, scale text, north arrow, legend, title, and map border. Some details regarding the map projection, contour interval (for a topographic map), source of data, name of the organization, and some explanatory notes will support the main message of a map.

Getting ready

In this recipe, you will design a thematic poster that presents a topographic map at the scale 1:5,000. Your poster will contain three data frames and a title, scale, legend, and dynamic text. The following table describes the shape and size of an old paper map:

Scale	Trapezoid		Grid
	Latitude	Longitude	
1:5,000	1' 15"	1' 52, 5"	500
			m
1:2,000	37.5"	56.25"	200
			m

The following screenshot represents the dimensions and geographic coordinates (latitude and longitude) for a sheet of a topographic map at the scale 1:5,000:

25º26'15" 44º48'45"	(longitude interval 1' 52",50) 49,43 cm	25º28'7,5" 44º48'45"
(latitude interval 1' 15") 46,40 cm	Topographic map 1:5000 L-35-111-D-b-2-III	(latitude interval 1' 15") 46,40 cm
25º26'15"		25º28'7,5"
44º47'30"	49,45 cm	44º47'30"



You have the final poster in PDF format at <drive>:\PacktPublishing\Data\ ExportingMaps\FinalMapLayout.pdf. Please use this example while you work with the exercise from the next section.

How to do it...

Follow these steps to create a map layout using ArcMap:

- Start ArcMap and open the existing map document MapLayout.mxd from <drive>:\PacktPublishing\Data\ExportingMaps.
- 2. To prepare the map data for print, you have to create a map layout in **Layout View**. Switch from **Data View** to **Layout View** by selecting **View** | **Layout View**.

A new toolbar has automatically been added: **Layout** toolbar. The tools on this toolbar can be used only in **Layout View**. To select, move, and resize the map elements on your map layout, you will use the **Select Elements** tool from the **Tools** toolbar. A selected map element will be outlined in blue and will have eight selection handles. If you place the mouse pointer over one blue selection handle, you will be able to resize the map element. Right-click on any selected map elements to change its properties.

3. Before starting work on your map layout, define the virtual page size. From File | Page and Print Setup | Map Page Size, uncheck Use Printer Paper Settings. For Page, select Custom as Standard Sizes. For Width, type 80, and for Height, type 115. For Orientation, select Portrait. Click on OK.


Layout View has two rulers: at the top and on the side of the virtual page. Let's adjust them:

4. Navigate to **Customize | ArcMap Options | Layout View**. You can open **ArcMap Options** directly by right-clicking on one of the rulers and selecting **Options**. Set the parameters as shown in the following screenshot:

CAD	Sharing	Display	Cache	Data Interop	erability
General	Data View	Layout View	Metadata	Tables	Raste
Appearan Stretd Show	v you work with you ce h contents when wi <u>h</u> orizontal guides <u>v</u> ertical guides dashed line around	indow is resized		ut view.	
<u>R</u> ulers V Sh <u>o</u> w		Units: Cer	ntimeters	•	
	Smallest	t <u>D</u> ivision: 0.	5 cm	•	
Grid					
Show	Hori <u>z</u> onta	Spacing: 0.	1 cm	v	
	Ver <u>t</u> ical	Spacing: 0.3	1 cm	v	
The grid v	vill not be shown if	the spacing is t	oo fine for the	e zoom level.	
Shap elem	ients to:				
Grid	(2)				
Margir	IS			×	
	Snap T	olerance: 0.1	5 cm	(3)	

-184

5. Click on Apply and on OK. To add guides, right-click on the vertical ruler from the left-hand side, and select Set Guide. Drag the light-blue ruler guide at 110 centimeters. Use Zoom In, Zoom Out, and Pan on the Layout toolbar to see the smaller division of the ruler. On the vertical ruler, add three more ruler guides at: 111, 40, and 5. On the top ruler, add three guides at 5, 6, and 75, as shown in the following screenshot:



185—

Resize the ${\tt Topographic Map 1:5,000}$ data frame and define a fixed scale for your data frame.

6. Select the data frame with the **Select Elements** tool. Right-click on the selected data frame and choose **Properties** | **Size and Position**. Set **Size**, **Position**, **Anchor Point**, and **Element Name**, as shown in the following screenshot:


ata Frame Propertie	s				×
General Data Fra Annotation Groups	me Coordinat Extent Indicato	e System ors Frame	Illumination Size and	Grids Position	Feature Cache Product Library
Position X: Y:	6 cm 109 cm	Size <u>W</u> idth: <u>H</u> eight:		50 cm 47 cm	
As Offset Dist		Element N	centage ve Aspect Ra ame bhic Map 1:50		
<u> </u>				Cancel	Apply

 Select the Data Frame tab. In the Extent section, click on the drop-down arrow and choose the Fixed Scale option. For Scale, type 5000 and click on Apply. Click on OK to close the window.

You can also manually resize and move the data frame using the **Select Elements** tool. Notice that your data frame is resized and moved. Also, the scale box on the **Standard** toolbar and **Zoom In / Zoom Out / Full Extent** on the **Tools** toolbar are gray. This indicates that the map scale value is locked.

8. Let's align the data to the data frame edge. To zoom the map layout, select Zoom In on the Layout toolbar (step 1) and draw a box that includes the top left corner of the data frame. Use the Pan tool on the Tools toolbar (step 2) to move the data in the data frame (step 3). The zoom tools on the Layout toolbar will not change the scale and map the extent of your data frame. Repeat the steps until the data is aligned to the edge of the data frame.





In the next steps, insert the title of the map:

- 9. Navigate to **Insert** | **Title**. Type Topographic Map 1:5,000 and click on **OK**. Select the title and drag it above the data frame. Right-click on the title and navigate to **Properties** | **Text**.
- 10. Select Change Symbol and set Size: 88. Select Save As and set the following parameters: Name: Map Title 5000, Category: LABELS, and Style: <drive>:\ PacktPublishing\Data\TOPO5k.style custom style.
- 11. Click on Finish and on OK. To unselect the title, click outside the map layout.

From time to time, be sure to save the map document as MyMapLayout.mxd at ... \Data\ExportingMaps.

In the next steps, you add a scale text and a bar to your map:

- 12. Navigate to Insert | Scale Text and select the Absolute Scale symbol, and click on OK.
- 13. Select and drag the scale element on the right-hand side of the map. Notice that the value is the fixed scale value of the data frame. Right-click on the selected map element and set **Properties** | **Format** | **Size**: 30. Save the text style. Click on **OK** to close the dialog.
- 14. Navigate to **Insert** | **Scale Bar** and select the Alternating Scale Bar 1 Metric symbol, and click on **OK** to accept the default properties and close the dialog box. Select and drag the map element to the right-hand side of the map below the numerical scale. Double-click on the scale to open **Alternating Scale Bar Properties**.



Exporting Your Maps _____

ale and Units	Numbers and Marks	Format	Frame	Size and Position
Scale				
<u>D</u> ivision value	:		100 m	(5)
Number of di	visions: Auto	A.		
Number of <u>s</u> u	bdivisions: 10	. (4)	
Show one	division <u>b</u> efore zero] (1)		
When resizing	J			
Adjust num	per of divisions		•	(2)
Units				
Division Units	:			
Meters			-	(3)
Label Position	:			
before bar			•	(4)
Label: Met	ers	<u>Symb</u>	ool	
<u>G</u> ap: 3.5	pt 📥			

15. For the **Scale and Units** tab, set the parameters, as shown in the following screenshot:



ale and Units	Numbers and Ma	arks Format	Frame	Size and Position
Frequency:				
divisions and f	first mid point		•	(1)
Position:				
Above bar			•	(2)
<u>G</u> ap: β.5ι	(3)	Number Form	nat	/
Use fraction	1 characters	Symb	ol	
Marks				
Erequency:				
divisions and f	first subdivisions		•	(4)
Position:				
Above bar			•	(5)
Division Height	: 3.5 p 🌲	Symb	ool	
Subdivision He				(6)
Subdivision He	ght: 3.5 p 🌲	Symb	ol	

16. Click on **Apply**. For the **Number and Markers** tab, set the parameters as shown in the following screenshot:

- 17. Select the Format tab, and set the parameters Text Size: 14 and Bar Size: 6.
- 18. Click on Apply. Save your scale style by navigating to Style | Style selector | Save: My 1:5,000 Scale Bar. Move the scale style to the custom style TOPO5k.style.
- 19. For the Size and Position tab, set the following parameters: Position X: 58 and Position Y: 105, Size Width: 16. Click on Apply and on OK.

In the next steps, you will insert the legend:

20. Navigate to **Insert | Legend**. By default, all layers are included in your legend (on the right-hand side). Change the order of layers in the Legend **Items** section: Elevation, ContourLine, WatercourseL, WatercourseA, Buildings, and LandUse.



21. For Set number of columns in your legend, type 1. Click on Next and accept the default values for the next two panels. In the symbol patch panel, select WatercourseA, and for Patch Area, select the Water body symbol. Select the Buildings layer and set Patch Area: Urbanized Area. Click on Next on the final panel and accept the default values. Click on Finish.

Let's refine the legend:

22. Right-click on the selected legend, navigate to **Properties** | **Layout**, and change the **Gaps** values, as shown in the following screenshot:

Legend Properties		×
General Items Layout	Frame Size and Posi	ition
Gaps		title gap
title gap (1) item gap column gap layer name gap group gap heading gap text gap vertical patch gap patch gap	14.00 pt 12.00 pt 0.00 pt 12.00 pt 12.00 pt 10.00 pt 8.00 pt 14.00 pt 12.00 pt	Title tayer 1 Layer 7 Group 1 Group 2 Class 1 Description 1
Line: Area:		ight: (2)
Text Wrapping		Fitting Strategy
Label width:	0 pt	Automatically adjust number of <u>c</u> olumns
Wrap <u>d</u> escriptions		✓ Shrink contents to fit frame
Description width:	0 pt	Minimum font size: 4 pt
Right to left reading		
		OK Cancel Apply

23. Select the Size and Position tab, and set the following: Position X: 60 cm and Position Y: 72 cm. Click on Apply to save the changes. Those are the main settings for a legend.

You can continue improving the legend by selecting the **Items** tab. You can change the label properties for every layer from the list. Let's test some options:

24. Select the ContourLine layer. For the Font section, choose Apply to the heading. Set Symbol | Size: 22. Click on Apply.



- 25. You can save the style of the legend for ContourLine. Make sure that the ContourLine layer is still selected before saving your style. Click on the **Style** button. Save your legend as ContourLine Legend. Keep clicking on **OK** to close all the dialog windows.
- 26. To move your new legend style (the Legend Items folder) from the default personal style file to TOPO5k.style, use **Customize** | **Style Manager**.

Let's insert a border around the map using a custom border style from TOPO5k.style:

27. Select the data frame using the **Select Elements** tool. Go to **Insert** | **Neatline** and set the parameters as shown in the following screenshot:

Neatline	x
Placement	Border
Place around selected element(s)	
Place around all elements	
Place inside margins	Background
Create separate neatline element	
Group neatline with element(s)	
Gap: Rounding:	Drop Shadow
23 pts %	
Advanced	OK Cancel

28. In the Border section, click on the Style Selector button. In the Border Selector window, click on More Styles to check whether TOPO5k.style is checked. Select the Map Frame 5000 symbol. Click on OK. To change the properties of the neatline, go to Data Frame Properties | Frame | Border.

Add a graticule (parallels and meridians) and a grid (rectangular coordinates). The grid will be superimposed on the graticule.

29. In the Table Of Contents section, right-click on the Topographic Map 1:5,000 data frame, and navigate to Properties | Grids | New Grid. Check Graticule, and for Grid Name, type Geographic coordinates. Click on Next. Check the Graticule and labels option. In the Intervals section, set Place parallels every | Min: 1 and Sec: 15. Set Place meridians every | Min: 1 and Sec: 52.5. Click on Next. Check only the Major division ticks option. Go to the next panel. Check Place a simple border at edge of graticule and Store as a fixed grid that updates with changes to the data frame. Click on Finish.



We want to reproduce the old map values of the geographic coordinates. For this reason, we defined such small intervals for meridians and parallels. You will refine the interval values and define your own origin in the next steps:

30. In View | Data Frame Properties | Grids, select Geographic coordinates, and click on Properties | Intervals. Set the parameters as shown in the following screenshot:

eference	Syst	tem Prope	rties	-	-	-		X
Axes	Inter	ior Labels	Labels	Lines	Hatching	Intervals		
Inter	val –							
X Ax	is:	0	0	1	[52.500000	"	(2)
Y Ax	is:	0	0	1		15.000000	"	
X Ori	igin:		0	26		15	"	(3)
Y Ori	igin:	44	0	47	· · · · · · · · · · · · · · · · · · ·	30	"	
)egre	44 es-Minutes al Degrees es and Dec	-Seconds) (1)	30		ļ

- 31. Click on Apply to save the changes. Select the Axes tab. For Major Division Ticks, add the line symbol named Grid from TOPO5k.style. Check Display ticks outside with Tick size: 23 pts. Select the Labels tab. For Label Offset, type 1 pts. Select Additional Properties and choose as Label type the Stacked option. Click on OK to close all windows. Inspect the results. Align the data to the data frame edges to have geographic coordinates for all corners of the data frame.
- 32. In Data frame Properties | Grids, add New Grid. Check Measured Grid, and for Grid Name, type Projected coordinates. Click on Next. Check the Grid and labels option. In the Intervals X Axis and Y Axis section, type 500 with unit as Meters. Click on Next twice to accept the default settings and click on Finish.

- 192

33. In Data frame Properties | Grids, select Projected coordinates, and click on Properties | Intervals. For Origin, select Define your own origin, and type 500,000 for both X Origin and Y Origin. Select the Labels tab. For Label Offset, type 1 pts. For Label Orientations, check only Left and Top. Select Additional Properties and choose Specify the number of digits in a group: 3. Select Number Format, check Number of significant digits: 6, and select Show thousands separators. Click on OK until all windows are closed.

Save your grids as My Geographic coordinates and My Projected coordinates.

- 34. In **Data frame Properties** | **Grids**, select the reference grid and click on **Style** | **Save**.
- 35. Use **Style Manager** to move your symbols from the *default personal style* file (the Reference Systems folder) to TOPO5k.style.

Let's insert some information regarding the coordinate reference system on your map:

36. Navigate to **Insert | Dynamic Text | Coordinate System**. Move the text box below the legend. Change the font size to 18.

A map layout can have one or more data frames with different coordinate reference systems, scales, and extent. Add two data frames in your map layout.

- 37. Navigate to Insert | Data Frame. In Data Frame Properties, rename the new data frame to Romania Pulkovo 1942. For Size and Position, set the following elements:
 - Position X: 5 cm; Position Y: 60 cm
 - Size Width: 25 cm; Size Height: 17 cm
 - Anchor Point: top left
 - **Define a fixed scale:** 3,000,000
- 38. Add the Counties.lyr layer in your data frame from ...\Data\ExportingMaps\ LayerFiles. In the map layout, add your data at the center using Pan tool from the Tools toolbar.
- **39.** Create a new data frame named: Europe ETRS89. For **Size and Position**, set the following elements:
 - **Position X**: 5 cm; **Position Y**: 40 cm
 - Size Width: 70 cm; Size Height: 35 cm
 - Define a fixed scale: 10,000,000



40. Add the Europe.lyr layer from ...\Data\ExportingMaps\LayerFiles. Add your data in the center of the data frame.

Let's define an extent indicator for this data frame. The data frame Europe ETRS89 will be the reference map, and the Romania Pulkovo 1942 data frame will be the inset map.

41. In **Data Frame Properties**, select the **Extent Indicators** tab, and move the Romania Pulkovo 1942 data frame to the right-hand side section **Show extent indicator** for these data frames. Click on the **Frame** button if you want to change the default symbol. Check the **Use simple extent** option. Click on **Apply** and on **OK** to close the window.

You obtained a red rectangle around a country from your Europe data frame. If you change the dimension of the Romania Pulkovo 1942 data frame, the red rectangle will be updated to the new extent.

Continue to add more map elements on your map layout to fill the center gap or to improve the final poster.

In the next steps, you will save your map and set up the printer:

- 42. Save the map document as MyMapLayout.mxd at Data\ExportingMaps.
- 43. Go to **Page and Print Setup**, and for **Printer Setup** | **Name**, choose a large format printer (plotter).
- 44. For **Paper Size**, select a proper printer paper size in accordance with the size of your map layout. Make sure **Orientation** | **Portrait** is checked. For **Map Page** | **Size**, check **Use Printer Paper Settings** and **Show Printer Margins on Layout**. Uncheck Scale Map Elements. Click on OK.
- 45. Navigate to File | Print, and for Printer Engine, choose Windows Printer. Set Output Image Quality to Normal. Click on OK. Before starting to print, go to File | Print Preview to check the final details.

How it works...

It is good practice to use a fixed scale for a data frame when you are working on a map layout.

Dragging the data in a map layout will not change the coordinates of your data.

By default, all inserted map elements will appear on the center of the graphic area.

You have noticed that the edges of your extent are curved. This is because the Romania Pulkovo 1942 data frame has defined a *projected coordinate system* and the Europe ETRS89 data frame has defined a *geographic coordinate system*.



If you have the same coordinate system (geographic or projected) for both data frames, then the extent will be straight.

The total length of your scale bar should not exceed a third of the width of your data frame. The **When resizing** | **Adjust number of divisions** option will update the number of divisions and will keep the distance represented by each division when you decide to change the length of your scale from 1:5,000.

You have already worked with an active data frame in *Chapter 3, Working with CRS*. If you select the data frame in the map layout, the name of the activated data frame is indicated with bold letters in the **Table Of Contents** section. When you work with multiple data frames in a map layout, always look at the state of data frames in the **Table Of Contents** section.

There's more...

A template contains a designed map layout with one or more data frames. A template can contain data as basemap layers. Every new map document is based on a normal template that contains a single empty data frame. The normal template is the **Blank Map** saved as Normal.mxt at %AppData%\ESRI\Desktop10.2\ArcMap\Templates. A map document mxd can be used as a map template.

You will create *your own template* to save time when you create another map at the scale 1:5,000 with the same components. Your custom template will contain Europe.lyr as a basemap layer and all map elements from the previous section:

- Start ArcMap and open an existing map document Template.mxd from <drive>:\
 PacktPublishing\Data\ExportingMaps. The map document contains three
 data frames. Only the Europe ETRS89 data frame contains data. Notice the source
 of data. Close ArcMap.
- 2. In Windows Explorer, right-click on the Template.mxd ArcGIS ArcMap document, and choose Copy. Go to %AppData%\Roaming\ESRI\Desktop10.2\ArcMap\ Templates and create a new folder, Custom templates. In this empty folder, right-click and choose Paste.



Because your template map contains a basemap layer, save Template. mxd from %AppData%\Roaming\ESRI\Desktop10.2\ArcMap\ Templates with relative pathnames. Open your template map with ArcMap, set the data source, and select File | Map Document | Properties. Check the Store relative pathnames to data source option.



- 3. Open ArcMap. In the ArcMap-Getting Started dialog, go to New Maps | My Templates | Custom Templates, and choose Template. Click on OK.
- 4. In the **Table Of Contents** section, right-click on the Topographic Map 1:5,000 data frame, and select **Activate**. Add the LandUse feature class from ...\Data\TOPO5000.gdb\LandUse.
- 5. Notice the update from the map layout. Save your map document as MyNewMap.mxd.

If you want all users of system to use a standardized template, copy <code>TemplateAllUsers</code>. mxd to a new folder named <code>MyOrganization</code> at <code><ArcGIS_HOME>\Desktop10.2</code>\ MapTemplates.

Next time, when you open ArcMap, you will get the following structure:

Q New Document	×
Choose a template for your new map	
New Maps My Templates User templates Custom Templates Templates Templates System templates Vorganization Standard Page Sizes Architectural Page Sizes North American (ANSI) North Ame	MyOrganization •
C:\Program Files (x86)\ArcGIS\Desktop10.2\MapTemp	lates\MyOrganization\TemplateAllUsers.mxd
Default geodatabase for this map:	What is this?
C: \Users\dana \Documents \ArcGIS \Default.gdb	• 🖄
	OK Cancel

Notice that the TemplateAllUsers.mxd template doesn't have data. The template contains only three empty data frames and specific map elements.

Exporting your map to the PDF and GeoTIFF formats

Even if your colleagues don't have ArcGIS, you still can share your map with them. You can export your map in:

- ► Raster format: This includes bitmap, Tagged Image File Format (TIFF), and Joint Photographic Experts Group (JPEG)
- Vector format: This includes Enhanced Metafile (EMF), Encapsulated PostScript (EPS), Adobe Illustrator (AI), and Portable Document Format (PDF)

Getting ready

PDF is a vector-based file format that supports the information coming for vector and raster sources. Use **Adobe Reader** to view the results of this recipe. You can download the software for free from www.adobe.com.

TIFF is a raster-based file format used mainly to store raster images. **GeoTIFF** is TIFF with the coordinate reference system embedded. It is used to store data such as aerial photography, satellite images, terrain digital elevation models, or scanned old maps.



Before starting, please refer to:

- Online Acrobat Help / Geospatial PDFs at http:// helpx.adobe.com/acrobat/using/ geospatial-pdfs.html
- The GeoTIFF website at http://geotiff. osgeo.org

How to do it...

Follow these steps to export your map to a PDF format using ArcMap:

- 1. Start ArcMap and open an existing map document FinalMapLayout.mxd from <drive>:\PacktPublishing\Data\ ExportingMaps\MyResults.
- 2. Select File | Export Map. For the Save As type, select the PDF (*.pdf) format. For File name, type MyTopographicMap300dpi.
- 3. Select the **General** tab. For **Resolution**, keep the default resolution: 300 **dots per inch** (**dpi**). Set **Output Image Quality** to **Normal**.



- 4. Select the Format tab. Select RGB for Destination Colorspace because you intend to use a laser printer for a quick preview of the results. If you intend to use commercial offset printing, you should use CMYK. See the There's more... part of the Modifying symbols recipe of Chapter 5, Working with Symbology. Make sure Embed All Document Fonts is checked. Accept all other default options.
- Select the Advanced tab. For Layers and Attributes, select Export PDF Layers and Feature Attributes. Check Export Map Georeference Information to access the georeference information from the PDF file. Click on Save.
- 6. Repeat the steps for a PDF with 72 dpi and save it as MyTopographicMap72dpi.
- Open the files with Adobe Reader. To see the layers and attributes of the features from your map, go to View | Show/Hide | Navigation Panel | Layers and Tree View. To see the geographic coordinates, go to Tools | Analyze, and select the Geospatial Location tool.

To save your map layout to a **Layout GeoTIFF** (*.tiff) file, you will need the **Esri Production Mapping** extension. This extension will allow you to check the following options: **Write World File** and **Write GeoTIFF Tags**. You also have a **Production** tab, where you can choose which data frame will define the coordinate reference system of the GeoTIFF file. GeoTIFF supports only one CRS at one point of time. Remember that your map layout contains three data frames with two different coordinate reference systems. If you don't have the extension, you can save as a TIFF, as follows:

- 1. Navigate to File | Export Map. For Save As, select the TIFF (*.pdf) format. For File name, type MyTopographicMap72dpi.
- 2. Select the **General** tab. For **Resolution**, type 72 dpi. Accept the default number of pixels. Accept all other default parameters. Click on **Save**.
- 3. Repeat the steps for a TIFF file with 300 dpi and save it as MyTopographicMap300dpi.

Compare the file size in Windows Explorer of the four files and notice the quality of maps.

How it works...

When you export your map to any format allowed, the **Export Map** | **Clip Output to Graphics Extent** option eliminates the white empty margin around your map elements.

In relation to the **Embed All Document Fonts** option from step 4, please be aware about the fonts used. Some fonts do not support embedding in a PDF file. Embedding means that PDF uses the same fonts as your map layout even if the file is opened on a platform that does not have the map's fonts (for example, Esri fonts). You can verify that your font is embeddable at **Microsoft typography** at http://www.microsoft.com/typography.



You can control what layers and their attributes should be transferred to the PDF format. In the **Table Of Contents** section, you can unselect the layers. To reduce the number of attributes for the visible layers, uncheck the attributes in **Layer properties** | **Fields**. An example of a PDF with restricted layers and attributes is RestrictedTopographicMap. pdf from the ...\ExportingMaps\MyResults folder.

The PDF vector format is used to display web maps. When you use **Pan** and zoom in your software, the displaying is quite fast. This format is not quite the best solution for print publishing because PDF could make small changes in font characteristics.

The TIFF format will build the map pixel by pixel. This format is used for print publishing. A high resolution will create a high-quality map with a price: a large file size (300 dpi/over 300 MB). When you use **Pan** and zoom in your graphics software, the displaying will take a while for the MyTopographicMap300dpi map. The labels and line symbols from the MyTopographicMap72dpi map are slightly jagged. However, this will not affect the quality of a **PowerPoint** presentation, for example.

Creating an atlas of maps

An atlas of maps is a collection of maps. Those collections of maps use spatial dataset series and other additional information. In accordance with *INSPIRE Metadata Implementing Rules Technical Guidelines*, a series is a collection of related datasets that share the same product specification.

The **Data Driven Pages** function allows you to generate a series of maps starting from a map layout and an index layer. An index layer is used to specify the dimension and the number of pages from the map book. Each feature from the index generates one output map. You can use a *regular grid*, a strip map that follows a linear feature, or any feature layer from the data frame as an index layer.

The general steps in generating a series of map pages are:

- 1. Creating a map layout.
- 2. Creating Grid Index Features.
- 3. Setting up the **Data Driven Pages** function.
- 4. Exporting the pages in PDF format.

When the **Data Driven Pages** function is enabled in your map layout, there will be a new tab in the **Export Map** window. The **Pages** tab will allow you to control the **Data Driven Pages** export.

Getting ready

You will create a series of maps at the scale 1:2,000, starting from the map extent of the scale 1:5,000. The map layout from the following section will contain two data frames with the same coordinate reference system. Every data frame contains the same layer structure. The Topographic Map 1:5,000 data frame will be unchanged in every output page. The map pages will be generated based on the Topographic Map 1:2,000 data frame content.

Before starting the exercises, please open the Map_L-35-111-D-b-2-III-1.pdf file from the ExportingMaps\MyResults folder. This PDF file is one of the final results in this recipe.

How to do it...

Follow these steps to create a map series at scale 1:2,000 using Data Driven Pages:

 Start ArcMap and open an existing map document DrivenPages.mxd from <drive>:\PacktPublishing\Data\ExportingMaps. Make sure that the data frame Topographic Map 1:2,000 is your current data frame or active (shown in bold in the Table Of Contents section).

Notice the red extent indicator from the Topographic Map 1:5,000 data frame. It's indicating the extent of the Topographic Map 1:2,000 data frame.

 Firstly, you will create a grid index in a new feature class. Open ArcToolbox, go to Cartographic Tools | Data Driven Pages, and double-click on the Grid Index Features tool, as shown in the following screenshot:

200

Chapter 7

Topographic map 1:5000 L-35-111-D-b-2-III		Grid Index Features
Ŷ		Generate Polygon Grid that intersects input feature layers or d Use Page Unit and Scale (optional) Map Scale (optional) 2000 Polygon Width (optional)
L-35-111-D-b-2-III-1	L-35-111-D-b-2-III-2	63 Centimeters Polygon Height (optional) 59 Polygon Grid Origin Coordinate (optional) X Coordinate 534603.3530000001 365826.8310000002
L-35-111-D-b-2-III-3	L-35-111-D-b-2-III-4	Number of Rows (optional) Number of Columns (optional) Starting Page Number (optional) 1
		Start labeling from the Origin (optional) Image: Cancel Concel Environments

- 3. For the Output Feature Class, go to ExportingMaps\LayerFiles\TOPO5000, and type Index2K. For Input Features, select Trapezoid5000. Check Generate Polygon Grid and Use Page Unit and Scale. Be sure that Map Scale is 2000. For Number of Rows and Number of Columns, type 2. For Starting Page Number, type 1. Accept the default values for the rest of the parameters. Click on OK.
- 4. Add Index2k in your data frame. For the Index2k layer, change the symbol to Hollow with Outline Color: Mars Red. Open the Index2k attribute table. Select the PageName field and right-click on it to select Field Calculator. Select the Load button, go to ExportingMaps\LayerFiles, and select the Index2000.cal file. Click on Open and on OK.



5. Select the Data Driven Pages toolbar from the Layout toolbar. A new toolbar has been automatically added: the Data Driven Pages toolbar. Navigate to the Data Driven Page Setup | Definition tab, and set the parameters, as shown in the following screenshot:

Set Up Data Driven Pages	×
	utput pages using a single layout. Each page ents are defined by the features in the index
Index Layer Data Frame: (2) Topographic Map 1:2000 Layer:	Optional Fields Rotation: none Spatial Reference:
Mame Field: PageName (4) ✓ Sort Field: PageNumber (5) ✓	PageNumber Page Number: none Starting Page Number: 1
Sort Ascending (6)	OK Cancel

- 6. Select the **Extent** tab and only check the **Center And Maintain Current Scale** option. This option will center every feature from the index layer in the middle of the Topographic Map 1:2,000 data frame and will keep the scale of 1:2,000. Click on **OK**.
- 7. In ArcToolbox, go to Cartographic Tools | Data Driven Pages, and double-click on the Calculate Adjacent Fields tool. For Input Features, select the Index2k layer. For Field Name, select PageName. Click on OK. To inspect the result, use the Open Attribute Table tool from the Data Driven Pages toolbar.

Let's add the index name for your maps:

- 8. Navigate to **Page Text** | **Data Driven Page Name**. The inserted map element will appear at the center of the graphic area. Right-click on the small rectangle selected and select **Properties** | **Change Symbol**. For **Size**, type 75, and click on **OK** twice to close the dialog boxes. Drag the index name above the data frame's title. Use the blue arrows from the **Data Driven Pages** toolbar to see how the data frame and the index name are being updated.
- 9. Save the map document as MyFinalDrivenPages.mxd at <drive>:\ PacktPublishing\Data\ExportingMaps.

You will save your maps in four different PDF files:

- 10. Navigate to File | Export Map. For the Save As type, select the PDF (*.pdf) format. For File name, type TopographicMap. Navigate to Options | General. For Resolution, type 100 dpi. Select the Pages tab. Check All (4pages). For Export Pages As, choose Multiple PDF Files (page names). Select the Advanced tab. For Layers and Attributes, select Export PDF Layers Only. Check Export Map Georeference Information. Click on Save.
- 11. With Windows Explorer, explore the results from the four PDF files.

How it works...

If you have multiple data frames in your map layout, you should activate the data frame for which you want to create a series of layout pages. The parameters **Polygon Width**: 63 cm and **Height**: 59 cm from step 3 represent the size of the data frame. Having a fixed scale extent for the data frame ensures you do not miss the **Map Scale (optional)** value.

To generate a correct index for scale 1:2,000:

- You used a reference layer named Trapezoid5000, which represents the extent of a map at scale 1:5,000
- You have specified two rows and two columns in the index layer that will cover the extent of the reference layer

These are the two final remarks about the previous exercise:

- Take into account that various standards or norms specify that symbols characteristics (for example, size) do not remain constant as the scale changes. For the Topographic Map 1:2,000 data frame, we used the symbols and annotation feature classes from the previous data frame (scale 1:5,000) for ease of work. Normally, you should create the symbols and annotation for the scale 1:2,000.
- ► We assumed that datasets have a positional accuracy corresponding to the scale 1:2,000. Therefore, we used the same dataset for both data frames.

You can display your data at any scale you want, but don't overlook the positional accuracy of the original dataset. It is a right decision to mention this aspect on your final map.



Exporting Your Maps -

Publishing maps on the Internet

The most common methods to share your maps are:

- ► Layer package (lpk)
- Map package (mpk)
- ► **Tile package** (tpk)
- Web map (a basemap layer and different data layers)
- Exported maps (for example, PDF file)

A layer package contains one or more layers (.lyr file) and the copy of the original data. Please remember that a layer file includes only the symbol and label definition, and the reference to the source data.

A map package contains a map document (.mxd file), the copy of the original data, and other documents (for example, a PDF file). A map package is used mainly for the vector format in order to edit, query, identify, or analyze data. You will create a map package in the next recipe.

A tile package contains the vector and raster formats. A tile package is used as a basemap (background reference information) and is structured in a set of tiles or images (for example, 256 x 256 pixels).



For more information about packaging and web maps, please refer to *ArcGIS Help (10.2)* online by navigating to **Desktop | Mapping | Sharing data through packaging** and also navigating to **Desktop | Mapping | Using web maps and GIS services**.

Getting ready

To publish your map on ArcGIS Online, you need:

- An Internet connection
- A web browser
- An Esri Global account

In your web browser, type http://www.arcgis.com to create an Esri Global account. Navigate to **Sign-up now** | **Create a Public Account**. Type all necessary information and click on **Review and Accept the Terms of Use and Create my account**.

204

How to do it...

Follow these steps to create a map package and share it on ArcGIS Online:

 Start ArcMap and open the SharingResults.mxd map document from <drive>:\PacktPublishing\Data\ExportingMaps.

Before starting to package our map, let's check the descriptive information about the SharingResults.mxd map document.

 From the File menu, select Map Document Properties, and change the name of Author. Add more Tags, such as topo maps, basemap, relief, and topography. Make sure that Store relative pathnames to data sources is checked. Click on OK.

Map Document Pro	operties X
General	
Eile:	naps\ExportingMaps\MyResults\MySharingResults.mxd
<u>T</u> itle:	Topographic map
S <u>u</u> mmary:	A topographic map at 1:5000 scale.
D <u>e</u> scription:	Topographic map which includes water features, contour lines, and elevation points. The index contour interval is 10 meters.
<u>A</u> uthor: Credits:	Your Name
_	
Tag <u>s</u> :	Packt Publishing training data, water, elevation, topo r
Hyperlink base:	
Last Saved:	7/13/2014 11:12:40 AM
Last Printed:	7/9/2014 12:57:35 PM
Last Exported:	7/13/2014 10:48:09 AM
Default Geodatabase:	C: \Users \dana \Documents \ArcGIS \Default.gdb
Pathnames:	Store <u>r</u> elative pathnames to data sources
Thumbnail:	Make Thumbnail Delete Thumbnail
	OK Cancel Apply



Exporting Your Maps -

3. In the **File** menu, for **Sign In**, enter your user name and password to sign in to ArcGIS Online. Navigate to **Share As** | **Map Package**, as shown in the following screenshot:

Map Package	— X —
	🗸 Analyze 🛛 🙀 Share 💿
Map Package	Map Package
Item Description	
Additional Files	Upload package to my ArcGIS Online account (3)
Sharing	MySharingResults
	◎ Save package to file
	H:\PACKT_PUBLISING\++ArcGIS Cookbook\7Exporting your m
	Include Enterprise Geodatabase data instead of referencing the data
	About creating a map package
	вис с соруш
	Share As 🛛 🙀 Map Package (2)
	Add Data
	🔢 Sign Out - DDaniela 🏾 🚺
	ArcGIS Online

- 4. In **Map Package**, specify where to save your map package by checking the **Upload package to my ArcGIS Online account** option. You can change the name of your package. Uncheck **Include Enterprise Geodatabase data**.
- 5. Select **Item Description**. For **Access and Use Constraints**, please type Packt Publishing will permit you to use this database by contacting contact@packtpub.com.
- 6. Select **Sharing**. Check the **Everyone (public)** option. You can also share the data only with members of a group. Validate your map for any errors by selecting the **Analyze** button from the upper-right corner:

206

– Chapter 7

ap Package					23
			🗸 An	alyze 🐺 S	Share 🔥
Item Description Sh: Additional Files	ring are your package with: Everyone (public) Members of these groups Geomatica/2011	1			
Prepare					□ >
😰 0 Errors 🛛 🫕 0 Warnings 🛛 🕕 0	Messages Se	arch Analyze Results			
Severity Status Code	Description		Name	Туре	Data
	There are	no items to show.			
Status: Complete	No items		Show or	nly unresolve	ed items 📃


7. Click on **Share** to create and share the MySharingResults package. Click on **Yes** to save the map document. You will see the following messages:

Packaging 🛛	Succeeded X
	Successfully created map package online. MySharingResults
Preparing data (Folder Size 2MB)	
Cancel	ОК



Exporting Your Maps

8. Open your web browser and go to www.arcgis.com. Sign in with your Esri Global account, and select **My Content**, as shown in the following screenshot:



- 9. **My Content** lists your **Map Package**. You can see item details of your package, or you can download or open it in ArcGIS for Desktop.
- 10. Explore by yourself all options from ArcGIS Online.

How it works...

 After you have finished exploring different options from ArcGIS Online, please delete the package from your online account. From the File menu, select ArcGIS Online. Click on My Maps and Data. Select the MySharingResults map package and click on Details. In the bottom-right corner, select Delete Item, and click on Yes. Return to your browser and check whether the map package was deleted from ArcGIS Online.

See also

 If you want to learn more about how to manage map documents and layers' and how to automate map production and printing, please refer to Chapter 3, Managing Map Documents and Layers and Chapter 5, Automating Map Production and Printing from the book Programming ArcGIS 10.1 with Python Cookbook, Eric Pimpler, Packt Publishing (2013)

208

In this chapter, we will cover the following topics:

- Preparing data for geocoding
- Geocoding addresses
- Geocoding with alternative names
- Creating and editing routes
- Creating and editing events
- Working with complex routes
- Analyzing events

Introduction

Geocoding is the process of converting the address information into spatial data that can be displayed on a map using an *address locator*. In accordance with the online ESRI GIS Dictionary, an address locator is *a dataset that stores the address attributes, associated indexes, and rules* that define the process of geocoding.

As an ArcGIS for Desktop user, you can store the address locator in a .loc file format stored in a folder or in an existing geodatabase as Locator. You can also share your address locator with everyone in your organization:

- ► As a locator package (.gpk) format with ArcGIS Online
- ► As a geocode service with ArcGIS for Server

The ESRI GIS Dictionary defines linear referencing as a method for storing geographic data using a relative position along an already existing line feature.



For more details about the geocoding and linear referencing concepts, please navigate to **Guide Books | Geocoding | Linear referencing** sections from *ArcGIS Help* (10.2) online at http://resources.arcgis.com/en/help/main/10.2.

Preparing data for geocoding

The geocoding process requires *reference data* that has address information stored in fields that correspond to the required elements of an address locator style. Reference data can contain point, polyline, or polygon geometry. Geocoding also requires *a nonspatial table with addresses* to geocode.

Getting ready

In this section, you will prepare reference data and a nonspatial table with addresses for the geocoding process.

Firstly, you will standardize the reference data according to the **US Address-Dual Ranges** address locator style, as shown in the following table:


HouseNum*	PreDir	PreType	StreetName*	SufType	SufDir
68	-	-	Dacia	Ave	-

The standardization process will split an address into standard fields required by a specific address locator style and will translate the address information into standard abbreviations. The US Address-Dual Ranges style considers that the odd numbers are on one side of a street and the even numbers are on the other side.

The dual ranges style works with polyline features as a data reference. Therefore, you will use the Street polyline feature class from the VeloGIS.gdb geodatabase.



Secondly, you will prepare a nonspatial table imported into your geodatabase. The table contains customer addresses taken from a larger database of an imaginary delivery service named Farm Food Delivery. In this table, you should have the address information in one field, as shown in the following screenshot:



How to do it...

Follow these steps to examine and standardize the reference data:

- 1. Start ArcMap and open an existing map document PrepareGeocoding.mxd from <drive>:\PacktPublishing\Data\Geocoding.
- 2. The reference layer for geocoding is the Streets feature class from ... \Data \ Geocoding \ VeloGIS.gdb \Planimetry.
- 3. Let's examine its attribute table. Right-click on the Street layer and select Open
 Attribute Table. The Left_From, Left_To, Right_From, and Right_To fields
 contain the street number ranges on the left-hand side and the right-hand side of the
 streets. The ZIP_Left and ZIP_Right fields store the ZIP code. The Name field
 contains the name and type of the street.



4. You have to break down the name of the street into two elements required by the US Address-Dual Ranges address locator: street name and street type. Open ArcToolbox and go to Geocoding Tools. Double-click on the Standardize Addresses tool to open the dialog box and set the parameters, as shown in the following screenshot:

Standardize Addresses	x
Input Address Data (1)	
Streets 💌 🖻	
Input Address Fields	
▼	
OBJECTID (2)	
Address Locator Style US Address - Dual Ranges (3) Output Address Fields	
HouseNum PreDir PreType	
StreetName (4)	
Select All Add Value Output Address Data (5) \ Geocoding\VeloGIS.gdb\Planimetry\Streets_StandardizeAddresse 🖻	
Dynamic Output Data. (optional)	+
OK Cancel Environments Show Help >:	>

5. For Input Address Data, select the Streets layer. For Input Address Fields, select OBJECTID and the Name field. Select US Address-Dual Ranges as Address Locator Style. Check only StreetName and SufType. For Output Address Data, go to ...\Geocoding\VeloGIS.gdb\Planimetry and type Streets_ StandardizeAddresses for the name of the dataset. Click on OK.

_212

6. You have obtained a new layer named Streets_StandardizeAddresses. Open its attribute table. The layer has two more fields: ADDR_SN (alias StreetName) and ADDR_ST (alias SufType). To toggle between the name and alias of the fields, select **Table Options**, and check or uncheck the **Show Field Aliases** option. Notice that the ADDR_ST field stores the corresponding abbreviations for street type. Your reference data is ready for geocoding your customer delivery addresses.

Continue the following steps to examine and prepare the CustomersFarmDelivery nonspatial table:

- 7. In the **Table Of Contents** section, make sure that the **List by Source** tab is selected. Right-click on the CustomersFarmDelivery table and click on **Open**. The table contains the name of customers and their addresses in separate fields. The US Address-Dual Ranges address locator requires that all street-related information be stored in a single field.
- 8. You will create a new field. Start the edit session to undo the edits in the event of a mistake. In the CustomersFarmDelivery table, select **Table Options** | **Add Field**. For the **Name**, type Address. For **Type**, select Text, and accept the default length of characters. Click on **OK**.
- 9. You will populate the values of the **Address** field by concatenating the following fields: StreetNumber, StreetName, TypeStreet, and ZIP. We will consider the street number as the house number.
- 10. Right-click on the **Address** field and select **Field Calculator**. You will use an existing expression. Select **Load** and select the US Address-Dual Ranges.cal file from ... \Data\Geocoding. Click on **Open** and then on **OK** to calculate the records. Inspect the result. Close the edit session. Your nonspatial table is ready for geocoding.
- 11. Save the map document as MyPrepareGeocoding.mxd at ... \Data \Geocoding.

You can find the results at ... \Data\Geocoding\ PrepareForGeocoding.

How it works...

As reference data, you can use feature classes or shape files. At step 5, you used two fields for address: OBJECTID and Name. The OBJECTID field will represent the numeric value for house numbers.

In the address table, you should have the entire address stored in one field. In the reference data, the address should be mostly in separate fields. The street polylines should connect to one another only at their endpoints. Before starting to use the reference data, check the connectivity of polylines using the following topological rules: **Must not have dangles** and **Must not intersect or touch interior**.

Geocoding addresses

The geocoding process requires four steps:

- 1. **Preparing reference data**: The following are the details of this step:
 - □ The point, line, or polygon geometry
 - L contains address information compatible with an address locator style
- 2. Choosing an address locator style: The following are the details of this step:
 - Let has a different number of required and optional fields
 - Depending on the address information from your resource data, choose the most suitable template to create an address locator
- 3. Creating an address locator: The following are the details of this step:
 - Rules for interpreting addresses (for example, odd street numbers are on the left-hand side of the street)
 - List of standard street components (for example, abbreviations such as Boulevard = Blvd)
 - Snapshot of reference data (for example, centerline streets)
- 4. Geocoding or matching addresses: The following are the details of this step:
 - Finding individual addresses
 - Creating point features based on a nonspatial address table

Getting ready

In the next exercise, you will create an address locator named Streets_Locator. Based on the address locator, you will geocode the CustomersFarmDelivery address table. Finally, you will try to improve the geocoding results by manually fixing the missing address matches.

How to do it...

Follow these steps to create an address locator and geocode the address table:

 Start ArcMap and open MyPrepareGeocoding.mxd to continue to work in the same geodatabase from <drive>:\PacktPublishing\Data\Geocoding\ VeloGIS.gdb.

If you did not succeed in finishing the previous step, please open an existing map document Geocoding.mxd from ...\Data\Geocoding\ PrepareForGeocoding. This map document uses a duplicate geodatabase named VeloGIS.gdb stored in the PrepareForGeocoding folder.

2. Open the **Catalog** window. Expand the VeloGIS.gdb geodatabase. Right-click on the geodatabase and navigate to **New | Address Locator**. Click on **Show Help** to read the descriptions for every section of the **Create Address Locator** window. Set the parameters, as shown in the following screenshot:

Address Locator Style US Address - Dual Ranges Reference Data			Reference Data
Reference Data	Role ddres Primary Table		classes and tables to be used by the address locator, along with their roles. Primary table— Defines the primary reference
✓m Field Map Field Name	Alias Name		dataset feature class for a locator, such as a street centerline feature class. This is a required table.
Feature ID *From Left *To Left	OBJECTID LEFT_FROM LEFT_TO	E	 Alternate Name table—Defines an alternate street name table that
*From Right *To Right Prefix Direction	RIGHT_FROM RIGHT_TO <none></none>		contains alternate names for the street or point
Prefix Type *Street Name Suffix Type Suffix Direction	<none> ADDR_SN ADDR_ST <none></none></none>		features. The table is required to have a JoinID that can be used to join to
Left Citv or Place			the primary table. This table is optional. • Alias table—
\Geocoding\VeloG	· · · · · · · · · · · · · · · · · · ·		Defines a place name alias table that contains place

- 3. For Address Locator Style, choose US Address-Dual Ranges, and click on OK. For Reference data, select the Street_StandardizeAddresses layer. To correct the error, select Primary Table for Role. In the Field Map section, check whether the required fields (fields with an asterisk) are mapped with the corresponding fields from the reference data. For Output Address Locator, go to VeloGIS.gdb, and save your locator as Streets_Locator. Click on OK and then on Save.
- 4. Streets_Locator has been added to VeloGIS.gdb.




- Let's test the address locator. Firstly, add the Geocoding toolbars by navigating to Customize | Toolbars. Click on the drop-down list and select Manage Address Locators. Click on the Add button and select Streets_Locator. Click on Add and on Close.
- 6. In the **Find Address** box, type the following individual address: 68 Dacia Ave. Press *Enter*. The address was not found. Retype the full address: 68 Dacia Ave, 20061, and press *Enter*. A green point location flashes. In the **Find Address** box, right-click on the address, and choose the **Add Point** and **Add Callout** options to place a point symbol and a callout label.
- Let's make the address locator more permissible when you type an address in the Find Address box. In the Catalog window, right-click on Streets_Locator. Navigate to Properties | Geocoding options and change the options, as shown in the following screenshot:

± F	Support intersections Reference data tables	True	
	Place name alias table		
	Input address fields		
	Outputs		
_	Geocoding options		
Ν	Minimum match score	85	
Ν	Minimum candidate score	75	
Ν	Match if best candidates tie	Yes	
S	Spelling sensitivity	80	
S	Side offset	12 (2)	
S	Side offset units	Meters	
E	End offset	3	
E	End offset units	Percent	E
Ð	Intersection connectors	& @ and at	
Ν	Match without house number	Yes (1)	
Ν	Match with no zones	Yes	-
L	eft side value	- L	
R	Right side value	R	
H	Performance		

8. On the **Geocode** toolbar, click on the drop-down list of **Select Address Locator** and select **Manage Address Locators**. Select Street_Locator and click on **Remove**. Click on the **Add** button and select again Streets_Locator. Click on **Add** and on **Close**. This will refresh the settings for your address locator.



- 9. In the **Find Address** box, retype 68 Dacia Ave, and press *Enter*. Now the address was found without the ZIP code 20061.
- 10. Find a location at intersections by typing: Dacia Ave & Drobeta St.
- 11. Find two relative locations by typing:
 - □ 20 meter east from 68 Dacia Ave
 - □ 20 meter south from Dacia Ave & Drobeta St
- 12. Continue to follow the steps to geocode addresses from the CustomersFarmDelivery nonspatial table, as shown in the following screenshot:



217—

13. Make sure that Street_Locator is selected in the Select Address Locator section from the Geocode toolbar. In the Table Of Contents section, right-click on the CustomersFarmDelivery table, and click on Geocode Addresses. Select Streets_Locator and click on OK. In the Geocode Addresses: Streets_locator window, set the parameters as shown in the following screenshot:

Geocode Addresses: Streets_Locator								
Address table: CustomersFarmDelivery	(1) 🗸 📑							
Address Input Fields Single Field (2) Full Address: 	O Multiple Fields							
Output	Address							
	 Create static snapshot of table inside new feature class Create dynamic feature class related to table 							
Output shapefile or <u>f</u> eat	ture class: (3) coding\VeloGIS.gdb\Planimetry\Customers							
Config <u>K</u> eyword:	DEFAULTS							
Advanced <u>G</u> eometry Options								
Geocoding Options	(5)							
About geocoding a table	of addresses OK Cancel							

14. Save the output as the Customers feature class in VeloGIS.gdb\Planimetry.

By choosing the **Create dynamic feature class related to table** option, you will create a dynamic geocoded output feature class. A composite relationship class will be created between the output feature class and the address table. Every modification in the address table will be automatically reflected in the address points.

15. Click on **OK** to start the geocoding process. You will obtain final statistics of the matched and unmatched customer addresses. Click on **Close**. We will come back later to those results. The Customers output layer has been added to the map. Open the Customers attribute table and the CustomersFarmDelivery table to inspect them.

218

You have noticed some additional fields in the Customers attribute table. Please navigate and refer to the **Guide Books** | **Geocoding** | **Locating addresses** | **About geocoding a table of addresses** section from *ArcGIS Help* (10.2) online to learn more about those new fields. Because your statistic results are not quite perfect, you will manually rematch the addresses, as shown in the following screenshot:

_		All Addresse	-					je result sets.	R	efresh	Rem	atch Automati	ically	Matched:	4 (50%)
ļ			Customers.Stat	Custom								RC Single		Tied:	1 (13%)
4		Point Point	M		100 37.22		93 Dacia Ave, 2 70 Dacia Ave, 2		R		cia Ave, ccia St. 2		5		
┫		Point	M	c	100		41 Dacia Ave, 2		R		cia St, 2 cia Ave.		5 6	Unmatcher	d: 3 (38%)
1		Point	M		100		4 Drobeta St. 20		R		eta St. 2		4		
ī	8	Point	Т	8	39.35		Aurel Vlaicu St,	20092	L		Vlaicu,		2		
1		Point	U		0						cia Av, 1		-1		
4		Point	U		0							St, 20092 -			
4	7	Point	U		0	A			I	10 Au	rei Viaici	st, 20521 -	-1		
,	Address:			4 Candid	lates									Can	didate details:
	Address AUR	EL VLAICU ,		Score	Side	Match	_addr	FromAddr	ToAddr	Pr	PreT	StreetName	SufType	FromAddr	47
				89.35	L	Aurel	Vlaicu St, 20092	47	49			Aurel Vlaicu	St	ToAddr	49
	──────────────────────			89.35	L	Aurel	Vlaicu St, 20092	39	41			Aurel Vlaicu	St	PreDir	
				89.35	R	Aurel	Vlaicu St, 20097	46	50			Aurel Vlaicu	St	PreType	
				89.35	R	Aurel	Vlaicu St, 20097	32	36			Aurel Vlaicu	St	StreetName	Aurel Vlaicu
	VOU	can fix o	do											SufType	St
		ling erro												SufDir	
	sper	iiiig en o	// 5											City	
														State	
														ZTP	20092
														Ref_ID	2
														User_fld	0
														Addr_type	StreetAddress
														Score	89.35
														Match addr	Aurel Vlaicu St, 200

- 16. In the Table Of Contents section, select Geocoding Result: Customers. From the Geocoding toolbar, select the Review/Rematch Addresses tool. Right-click on the Customers.Status field and select Sort Ascending to sort the values.
- 17. In the **Geocoding results** table, select the row with **Customers.ObjectID**: 8 and with **Customers.Status**: T. In the **Address** panel, the address is incomplete because it contains only the name of the street. You have four candidates for this address in the **Candidates** section. You should choose one of them to change the **Status** value.
- 18. Select the first candidate and read the candidate details. Click on Match and on the Refresh button. Notice that Customers.Status has changed from T (tied) to M (matched) and that the Customers.Match type has changed from A to M (manually match).


219—

- 19. If you want to have a score of 100, firstly, select again the first candidate, and click on Unmatch. Secondly, change Full Address from AUREL VLAICU to AUREL VLAICU ST. The score for all four candidates has been changed to 100. Select the first candidate, and click on Match and Refresh. Right-click on the Customers.Status field again and select Sort Ascending to sort the values.
- 20. In the table, select the row with **Customers.ObjectID**: 5 and with **Customers.Status**: U (unmatched). In the **Address** panel, for **Full Address**, correct the type of street from S T to ST. Click on the empty space of the **Candidates** section. Select the candidate that has appeared and click on the **Match** button. Notice that **Customers.ObjectID**: 5 has **Status**: M and **Score**: 100.
- 21. There are two unmatched addresses left. You have two options:
 - Accept the unmatched status.
 - The number of the house is wrong. In the table, select the record, and click on **Pick Address from Map**. Drag the **Interactive Rematch** dialog box to see the map. On the map, right-click on the chosen location, and select **Pick Address**. A new point has been added and **Customers.Match** has been changed to PP (Pick by Point). Click on **Refresh**.
- 22. Let's change the 87.22 score for **Customers.ObjectID**: 2 and control the number of candidates by selecting **Geocoding Options**. Change the following parameters: **Spelling sensitivity**: 95 and **Minimum Candidate score**: 60.
- 23. The goal is to see more candidates for an address but still keep **Minimum match score** higher. Click on **OK**. Click on **Refresh**.
- 24. Let's inspect the consequences. Select the row **Customers.ObjectID**: 2. Notice that **Full Address** has two errors and there is no candidate. This is because you increased **Spelling sensitivity** to 95 and the spelling errors are not accepted by the new **Spelling sensitivity** value.
- 25. If you correct the errors by changing DACCIA to DACIA, and ST to AVE, the previous candidate will show up. Click on the **Unmatch** button to unmatch the existing address and then click on **Refresh**. Select the candidate and again click on **Match**. Notice that the **Score** value has been changed to 100.
- 26. Select the row with Customers.ObjectID of 4 and 5. Notice that address has one more candidate with a score below 70. Select again Geocoding Options and change Minimum Candidate score to 70. Click on OK. By increasing Minimum Candidate score, the second candidate for the Customers.ObjectID of 4 and 5 have disappeared.
- 27. Close the **Interactive Rematch** dialog box. The Customers layer has been updated according to your last settings.

Let's test the composite relationship between those two tables.



28. Start the edit session to change an address from the CustomersFarmDelivery table and see the changes in the Customers layer, as shown in the following screenshot:



- 29. In the CustomersFarmDelivery table, select the record with **OBJECTID** as 1. In the **Address** field, change the number of the street to 95. Click on the **Related Tables** button and select the Customers_geocode_rel: geocodes relationship. The point feature from the Customers layer is now selected, and the Match_addr and Full Address values are automatically updated. Press the *F5* key to redraw the map. The point was moved according to the new address.
- **30.** Add a new customer in the CustomersFarmDelivery table. Let's suppose that Customer 9 will have the following address: 50 Aurel Vlaicu St, 20097. Fill the empty cells with the corresponding address information.
- 31. Look at your map while you are selecting **View** | **Refresh**. A new point has been added. Notice that the Customers attribute table has been updated with a new record. Save the edits and stop the editing session.
- 32. Save your map document as MyGeocoding.mxd.

You can find the results of this recipe in the **Geocoding** folder at \ldots \Data\Geocoding. Please do not modify the geodatabase from this folder. It will be used in the next recipe.

How it works...

The point and callout created at step 6 are graphic elements stored in your map documents. To move or delete them, use the **Select Elements** tool and the *Delete* key. The point features created from the address table at step 13 are stored as feature classes in your geodatabase.

Also, at step 13, you chose dynamic geocoding. This option is possible when your address table and the geocoded resulted feature class are stored in the same geodatabase. Dynamic geocoding refers only to the address table changes.

Later on, if you load more street centerlines in your reference data, the changes will not be reflected in the snapshot of the data from your address locator. To update your address locator, you have to *rebuild* it or create *a new* address locator.

At step 22, by lowering the **Spelling sensitivity** and **Minimum match score** values, you will obtain more matched addresses after the geocoding process. If you lower **Minimum candidate score**, you will find more potential candidates to match.

A 100 value for **Minimum match score** is considered a perfect match. A range from 80 to 99 for the match score is considered to be a good match. **Minimum match score** lower than 60 is not recommended. An address with a match score below the minimum value is considered to be unmatched.

Geocoding with alternative names

To locate an address, you have two more alternatives:

- Name aliases (for example, the 91 Dacia Ave address is known as Elementary School)
- Alternative names (for example, Dacia Avenue is a small section of the road called E60; E60 is part of the European Road Network)

The address locator with a name alias needs a supplementary table that must contain two required fields: the alias place name and the corresponding address. Your address locator will use this input table to search the address of the alias place name.

The address locator with alternative names needs an alternate name table that will contain specific fields in accordance with the address locator style (for example, prefix and suffix type, street name, and prefix and suffix direction). The alternate name table and the primary reference feature attribute table must contain the common Join ID field. Those two tables will join in a Many to Many relationship based on the common field.



Getting ready

You will geocode the <code>PointOfInterest</code> address table using a composite address locator, as shown in the following screenshot:

ArcCatalog - H:\PACKT_PUBLISING\	\Data\Geocoding\CompositeGeocoding\VeloGI						
	[] [] [[[[[[[[[[[[[[[[[Ŧ					
	coding\CompositeGeocoding\VeloGIS.gdb\F 👻 😴						
Catalog Tree 🛛 🕂 🗙	Contents Preview Description						
Geocoding	OBJECTID * Address	ZIP					
CompositeGeocoding Image: C		20052					
Composite_ParcelStreet	3 41 Aurel Vlaicu St	20092					
Parcels_PlaceAlias	4 Drobeta St 2	20521					
Streets_AlternateName		20521					
Planimetry		20521					
Buildings		20521					
Customers		20521					
Customers_geocode_rel		20521					
	11 20 meter south from Dacia Avenue & Drobeta St						
Point_byComposite Point_byParcel Point_byStreet SideWalk	(1) location by street address;	20321					
Streets Streets Streets StreetsP	(2) location by place name alias;						
AlternativeNameStreets	(3)location by street intersection and alternate	e nam					
 BucharestDistricts CustomersFarmDelivery 	(4)relative location by street intersection.						
PlaceAlias PointsOfInterest							
CompositeGeocoding.mxd	Preview: Table						
ile Geodatabase Table selected							

The composite locator will combine the functionality of two individual address locators:

Address locator	Parcels_PlaceAlias	Streets_AlternateName					
Address locator style	US Address-Single House	US Address-Dual Ranges					
Reference data	Parcels (polygon features)	StreetStandardizeAddresses (polyline features)					
Alternative searches	Place aliases based on the PlaceAlias table	Alternate names for streets using the AlternativeNameStreets table					
	The PlaceAlias and AlternativeNameStreets tables are already created in the VeloGIS.gdb geodatabase.						



If you worked on all previous exercises in VeloGIS.gdb from <drive>:\
PacktPublishing\Data\Geocoding, skip step 1 from the next section, and prepare your
Street StandardizeAddresses feature class for geocoding by:

- Adding a Join ID [Short integer] field
- Filling the Join ID field with the following values: 100 for street Aurel Vlaicu;
 101 for street Dacia; and 102 for street Drobeta

Add in your map document the following tables: PointsOfInterest, PlaceAlias, and AlternativeNameStreets.

Otherwise, please use the data and map document from <drive>:\PacktPublishing\ Data\Geocoding\Geocoding. The folder contains a duplicate VeloGIS.gdb geodatabase that will help you to succeed in the next steps.

How to do it...

Follow these steps to geocode addresses with place aliases and alternate names using a composite address locator in the ArcCatalog context menu:

- 1. Start ArcCatalog. In the Catalog Tree section, go to <drive>:\PacktPublishing\ Data\Geocoding\Geocoding.
- 2. Expand the VeloGIS.gdb geodatabase. Right-click on the geodatabase and navigate to New | Address Locator. Select US Address-Dual Ranges as the address locator style. Choose as reference data the Street_StandardizeAddresses feature class for Primary Table, and choose as reference data the AlternativeNameStreets table for Alternate Name Table. Perform the steps shown in the following screenshot:

224

US Address - Dual Ranges (1)			2
eference Data			
		(2)	2
		Role	
Geocoding\VeloGIS.gdb\Planimetry\Street	-		×
Geocoding\VeloGIS.gdb\AlternativeNameS	treets	Alternate Name Table	
4			
		•	
ield Map			
Field Name	Alias Name		
Primary Table:Feature ID	Streets_StandardizeA	Addresses:OBJECTID	
*Primary Table:From Left	Streets_StandardizeA	Streets_StandardizeAddresses:LEFT_FROM	
*Primary Table:To Left	Streets_StandardizeAddresses:LEFT_TO		
*Primary Table:From Right	Streets_StandardizeAddresses:RIGHT_FROM		
*Primary Table:To Right	Streets_Standardize/	Addresses:RIGHT_TO	
Primary Table:Prefix Direction	<none></none>		
Primary Table:Prefix Type	<none></none>		_
*Primary Table:Street Name	Streets_StandardizeAddresses:ADDR_SN		
Primary Table:Suffix Type	Streets_StandardizeA	Addresses:ADDR_ST	
Primary Table:Right Additional Field	<none></none>		
Primary Table: Altname JoinID (3)	Streets_StandardizeA	-	
*Alternate Name Table: JoinID	AlternativeNameStree	ets:JOIN_ID	
Alternate Name Table:Prefix Direction	<none></none>		_
Alternate Name Table:Prefix Type	<none></none>		
Alternate Name Table:Street Name (4)	AlternativeNameStree		Ξ
Alternate Name Table:Suffix Type	AlternativeNameStree	ets:STTYPE	
Alternate Name Table:Suffix Direction	<none></none>		-
		151	
utput Address Locator		(5)	
k	Geocoding\VeloGIS.gdb\S	treets_AlternateName	12

- 3. Most of the fields will match. Be careful about the following fields: for Primary Table/ Alternate Name Table: JoinID, choose the common field JOIN_ID. Save the address locator in your geodatabase. Right-click on Streets_AlternateName and navigate to the Properties | Geocoding options. Select Yes for the Match without house number and Match with no zones options. Click on OK.
- 4. Create a new **Address Locator**. Select US Address-Single House as the address locator style. This address locator style allows you to find an address point using polygon features as reference data.

225—

5. Choose as reference data the Parcels feature class for **Primary Table** and the PlaceAlias table for **Alias Table**. The red X indicates an error. To correct the error, match the required fields as shown in the following screenshot:

Address Locator Style US Address - Single House	(1)		
Reference Data	"		
		()	
		(2	
		Role	+
\Geocoding\VeloGIS.gdb\Planimetry\Par	rcels	Primary Table	
\Geocoding \VeloGIS.gdb \PlaceAlias		Alias Table	
			×
4		III	•
			r
Field Map			
Field Name	Alias	Name	
Primary Table:Feature ID	Parc	els:OBJECTID	
*Primary Table:House Number (3)	Parc	els:StreetNumber	
Primary Table:Side <no< td=""><td>ne></td><td></td></no<>		ne>	
Primary Table:Prefix Direction <no< td=""><td>ne></td><td></td></no<>		ne>	
Primary Table:Prefix Type	<nor< td=""><td>ne></td><td></td></nor<>	ne>	
*Primary Table:Street Name (4)	Parc	els:STREETNAME	
Primary Table:Suffix Type Par		els:STREETTYPE	E
Primary Table:Suffix Direction	<nor< td=""><td></td><td></td></nor<>		
*Alias Table:Alias (5)		eAlias:Name	
*Alias Table:Street	Place	eAlias:Address	
Alias Table:Citv	<nor< td=""><td>ne></td><td></td></nor<>	ne>	
•			•
Output Address Locator			
(6) \Geocoding \Geocoding	VeloGIS	.gdb\Parcels_PlaceAli	as 📂

- 6. Change the properties of the new Parcels_PlaceAlias address locator by selecting **Yes** for the **Match without house number** and **Match with no zones** options. Click on **OK**.
- 7. Let's create a composite address locator. Right-click on the geodatabase and navigate to New | Composite Address Locator. For Address Locator, add Parcels_PlaceAlias and Streets_AlternateName address locators. Name the Output Composite Address Locator as Composite_ParcelStreet. Click on OK. Right-click on Composite_ParcelStreet and click on Properties. Inspect the default settings.

226

- 8. In the **Participating Address Locators** panel, select Parcels_PlaceAlias to activate its individual properties. Navigate to **Properties | Geocoding options**, and select **Yes** for the previous house and zones matching options. Click on **OK**. Similarly, change the properties of the second address locator.
- 9. Let's geocode the addresses. In ArcCatalog, right-click on the PointOfInterest table, and select **Geocode Addresses**. In the **Choose an Address Locator to use** popup window, choose Composite_ParcelStreet, and click on **OK**. Continue to set the following parameters:
 - Address table: PointOfInterest
 - Address Input Fields: Single Field
 - Single Line Input: Address
 - Output feature class: ... VeloGIS.gdb\Planimetry\ Point_ byComposite
- 10. Click on **Geocoding Options**, and for **Intersections** | **Connectors**, type &, and click on **OK**. Your statistic results are not quite perfect and you should manually rematch the addresses.
- 11. Try to repeat the last two steps to geocode the PointOfInterest table based on the individual address locators:

Output feature class	Point_byParcel	Point_byStreet
Address locator	Parcels_PlaceAlias	Streets_AlternateName

12. Use ArcMap to see the three-point feature classes. Symbolize the new layers and examine the results. Improve the geocoded address results from the Point_byComposite feature class.

You can find the results of this recipe in the CompositeGeocoding folder at ... \Data \ Geocoding.

How it works...

A composite address locator geocodes an address table using the functionality of multiple address locators in one geocoding process. The next table shows the advantages and disadvantages of using a simple address locator or a composite one:

Address locator	Advantages	Disadvantages
Streets_AlternateName	This supports intersections.	There is low position accuracy.
	There is a high number of matching addresses.	
Parcels_PlaceAlias	There is high position accuracy.	This does not support intersections: Properties About the locator Support intersections : False
Composite_ParcelStreet	There is high position accuracy.	Trying to have a high number of matching addresses, your
	This supports intersections.	composite locator will use the most accurate locator first
	There is a high number of matching addresses.	(parcel) and the least accurate second (street). In the end, you will obtain a low accuracy result.

By choosing a composite address locator, you can improve the geocoding results, but you cannot compensate for the quality of address information from your reference data: *garbage in, garbage out.*

Creating and editing routes

A route is a linear feature that has a measurement system (for example, distance or time) and a unique identifier. Routes are stored in a route feature class (standalone feature class or in a feature dataset). The vertices of a route contain the *x* and *y* coordinates and a measure value or *m* value. Measure units are independent of map units. Measure values do not have to begin at zero and should be increased in the same direction.

Getting ready

In this section, you will create a route feature class that will store three simple routes that represent three different bus lines from your town: *bus 133*, *bus 79*, and *bus 135*. Your routes will be created from scratch using the **Trace** tool.


How to do it...

Follow these steps to create and edit simple routes in ArcMap:

- Start ArcMap and open the existing map document Routes.mxd from <drive>:\ PacktPublishing\Data\LinearReferencing. Open the Catalog window. Expand the VeloGIS.gdb geodatabase.
- 2. You will create a new route feature class. Right-click on the geodatabase and navigate to New | Feature class. For Name, type BusRoute_m. For Type, choose Line Feature. Under Geometry Properties, check Coordinates include M values. Used to store route data. Go to the next panel. Navigate to Add Coordinate System | Import, go to VeloGIS.gdb, and select the Street feature class. Accept the default settings from the next two panels. In the attribute table panel, add a new field that will store the unique identifiers of the routes. For Field Name, type RouteID. For Data Type, select Short Integer. Click on Finish. The empty BusRoute_m layer has been added in the Table Of Contents section.

That name of the BusRoute_m route feature class suggests the measure units (letter m refers to meter). It's good practice to document the measurement system and measure units in feature-class metadata.

3. In the Catalog window, right-click on BusRoute_m, and select Item Description. Select the Edit button, and in the Overview | Item Description | Description (Abstract) section, type: Bus routes. The measurement system is distance. The measure units are meters.. Click on Save and then on Exit.



Let's add three routes in the ${\tt BusRoute_m}$ layer, as shown in the following screenshot:

- 4. Start the edit session from the Editor toolbar. Set the editing environment: on the Editor toolbar by navigating to Editor | Snapping | Snapping Toolbar; select Point, End, Vertex, and Edge. From Snapping | Options, set Tolerance: 5 pixels and Show tips. In the Table Of Contents section, select List by Selection, and make BusRoute m the only selectable layer.
- 5. Open the Create Feature window to see the feature templates. Select the BusRoute_m layer. Under Construction Tools, select Line. On the Editor toolbar, click on the Trace tool. You will digitize the new routes based on the Street reference layer. First click on the Start Bus 133 point and digitize the route by tracing along the Street layer features until the End Bus 133 point. Press the F2 key to finish the sketch. Click on the Attribute button, and for RoutelD, type 133. Notice that your SHAPE geometry is Polyline M. This M means that your linear feature coordinates include measure values.



- 6. Repeat the previous step to create the routes 135 and 79.
- Save the edits and clear the selected features. Turn off the Street layer to better see the routes from the BusRoute_m layer. Symbolize the routes based on the RouteID field: Layer Properties | Symbology | Categories | Unique values.

At step 3, you already decided to use distance for your measurement system. You will assign measures to your new routes:

- 8. On the **Editor** toolbar, click on the **Sketch Properties** button. To see the vertices' coordinates, select route number 133 with the **Select Features** tool, and click on **Edit Vertices**.
- 9. Your M values are unknown (NaN-Not a Number). In the Attribute window, you already noticed the value of SHAPE_Length: 132.668 for RouteID: 133. You have the following two options:
 - Enter manually in the Edit Sketch Properties window, the start and end measures: Point 0: 0.00 and Point 4:132.668. In the map, right-click on the selected route and go to Route Measure Editing | Calculate NaN. Notice the values in the Edit Sketch Properties window. Close the window. If you want to return to the NaN values, choose Drop Measures.
 - In the map, right-click on the selected route, and go to Route Measure
 Editing | Set From/To. In the second cell, type the value 132.668. Press the Enter key to close and calculate the vertices' measure.

For the bus route number 133, you measured with a total station (surveying instrument) the 75 meters between the street intersections **1** and **2** (underlined in the previous screenshot by two circles). You will use this more accurate distance to update the segment measures of the route. This method is known as **calibration**. Firstly, add the **Route Editing** toolbar from the **Editor** toolbar by navigating to **Editor** | **More Editing Toolbars**. On the **Route Editing** toolbar, add the **Calibrate Route** tool from **Customize** | **Commands** | **Categories** | **Linear Referencing**.

- 10. Select route number 133. On the Route Editing toolbar, click on the Calibrate tool. Move the dialog box to see the map. Select Add Calibration Points Tool. In the map, snap the mouse pointer to the first intersection, and click on it once. Snap the mouse pointer again to the second intersection. Notice that two records are added in your Calibrate Route window. For the first record, type New M: 20.944. For the second record, type New M: 95.944. In the Options panel, check Interpolate between points, Extrapolate at the end, and Use existing measures. Click on Calibrate Route.
- 11. Open the **Edit Sketch Properties** window to check the results. Notice that the last measure value has been changed to 136.783. Now your measures reflect the reality from the field.

12. Assign measures to the last two routes: 135 and 79. Try to calibrate route number 79 using the same segment value between the two street intersections. Save the edits and stop the editing session.

Let's find a specific section along the route using the **Find** tool from the **Standard** toolbar:

- 13. Click on **Find** | **Linear Referencing**. Choose BusRoute_m and click on **Load Routes**. Choose route number 133. For **Type**, check the **Line** option. You want to find the section of route 133 from 25 meters to 75 meters from the start of the route. Set for **From**: 25 and for **To**: 75. Click on **Find**.
- 14. Select the record and right-click to explore the options. You can flash the segment. You can also **Draw Route Location**. You should turn off the BusRoute_m layer to see the segment that is a graphic element stored only in your map documents. To work with it, use the **Select Elements** tool from the **Drawing** toolbar or the **Standard** toolbar.

Let's find the measure value for a point along the route using the **Identify Route Location Results** tool from the **Route Editing** toolbar:

- 15. Click on the **Identify Route Location Results** tool. In the map, click on the first street intersection until you see all three routes in the **Identify Route Location Results** window. Inspect all of them. The **Measure** field displays the measure units (*m* value) calculated from the start of the route.
- **16.** Save your map document as MyRoutes.mxd at ... \Data\LinearReferencing.

You can find the results of this recipe at ... \Data \LinearReferencing\Routes.

How it works...

A route can be edited or updated in an ArcMap **Edit** session. At step 9, the **Use existing measures** option will constrain the interpolation process to use your measured value for the vertices of the calibrated segment (75 meters) instead of the distance value calculated from the vertices' *x* and *y* coordinates (72.327 meters).

There's more...

If you want to store routes with different measure units, you should separate them into different route feature classes. You can also update a route feature by following two steps: edit the route geometry (move, add and delete vertices, merge, and add new features) and re-measure the route (entire route or a portion of the route) using the **Define Line Portion** tool from the **Route Editing** toolbar. If the tool is not on your toolbar, you can add it by navigating to **Customize | Customize mode | Commands | Categories | Linear Referencing**.

Creating and editing events


A route event is a point or linear feature that occurs along a route feature. Route events are stored in tables called route event tables. A route table contains a route identifier field (for example, RouteID) that associates a specific route to the route point or linear event. Based on this route identifier field, a route table can store multiple events associated with a single route or can reference multiple routes. Also, multiple route events can reference a single route.

In ArcMap, you can create a layer of point or line features based on the information from the route event table. When you change a value in the route event table, the shape of the event (point or line) is automatically moved.

The features from the event layer are stored in a table and not in a feature class. You can export those event features to a feature class, but the dynamic connection between the route event table and routes will be lost.

Getting ready

In this recipe, you will create two route event tables, as shown in the following screenshot:



Firstly, the BusStop point route event table will have the following special fields: RouteID, Loc M, and Offset. BusStop refers to the bus stops along the bus routes.

Secondly, the MaximumSpeed line route event table will have the following special fields: RouteID, From_M, To_M, and Offset. MaximumSpeed refers to the speed restriction segments along the bus routes.

The field <code>RouteID</code> (route identifier field) defines the connection between the route and the route events. Lo_M, <code>From_M</code>, and <code>To_M</code> are measure location field(s). Offset represents the symbol translation from the route in map units.

You can continue to work in your map document MyRoutes.mxd and skip step 1.

If you didn't succeed in finishing the previous exercise, start with step 1.

How to do it...

Follow these steps to create events using ArcMap:

- 1. Start ArcMap and open the existing map document StartEvents.mxd from <drive>:\PacktPublishing\Data\LinearReferencing\Routes. Open the Catalog window. Expand VeloGIS.gdb from the same location.
- 2. You will create a route event table for point events. Right-click on the geodatabase and navigate to **New | Table**. For **Name**, type BusStop. Accept the default settings from the next panel. Add the following new fields:
 - RouteID with Data Type: Short Integer. This field will store the unique identifiers of the routes.
 - □ Loc_M with **Data Type**: Double.
 - Offset with **Data Type:** Short Integer and **Default Value:** 6.
- 3. Click on **Finish**. Your table has been added in the **Table Of Contents** section. To see the table, select the **List by Source** view.
- 4. You will create a new route event table for *line* events. Right-click on the geodatabase and navigate to **New | Table**. For **Name**, type SpeedLimit. Accept the default settings from the next panel. Add the following new fields:
 - RouteID with Data Type: Short Integer
 - From_M with Data Type: Double
 - **D** To M with **Data Type**: Double
 - Offset with Data Type: Short Integer and Default Value: 1
 - MaximumSpeed with Data Type: Short Integer and Default Value: 50

234

5. Click on Finish.

You now have two empty tables. Let's populate those tables. Open the YourEvents. pdf file from ... \Data\LinearReferencing. The file contains all information necessary to complete the route event tables:

- 6. Open the table BusStop. Start an edit session. Click inside the first empty cell under the RouteID field and type 133. For Loc_M, type 7. The Offset field is already populated with the default value 6. Notice also that the ObjectID field value is automatically generated. Continue to complete the table with the next 13 records using the information from the YourEvents.pdf file. Save the edits.
- 7. Open the SpeedLimits table. Complete the table with nine records. Save the edits and stop the edit session.

Let's create the point event layer based on the BusStop route event table:

- 8. In the **Table Of Contents** section, right-click on the BusStop table, and select **Display Route Events**. In the dialog box, set the following parameters:
 - Route Reference: BusRoutes and Route Identifier: RouteID
 - For Event Table | BusStop, select Route Identifier: RouteID
 - Check Point Events: Occur at a precise location along the route
 - Measure: Loc M and Offset: Offset; click on OK
- The new layer named BusStop Events has been added in the Table Of Contents section. Symbolize the point route event layer: Layer Properties | Symbology |
 Symbol | Style References | Public Sign: Bus.
- 10. Add labels to the event layer: Layer Properties | Labels | Label fields: RouteID. Don't forget to check Label features in this layer. Click on OK. Explore the attribute table of BusStop Events.

235

Let's create the line event layer based on the SpeedLimits table. On the **Route Editing** toolbar, click on the **Add Route Events** tool, and set the parameters as shown in the following screenshot:

Add Route Events	×		
	ects with locations measured along routes. A table ts can be added to the map as a layer.		
Specify the routes r	eferenced by the events in the table		
(1) Route Reference	e: BusRoutes 🔹		
Route Identifier:	RouteID		
Specify the table co	ntaining the route events		
Choose a table from	n the map or browse for another table.		
(2) Event Table:	SpeedLimit 🔻		
<u>R</u> oute Identifier:	RoadID		
Choose the type of	Choose the type of events the table contains:		
Point Events	: Occur at a precise location along a route		
(3) Line Events: 	Define a discontinuous portion of a route		
Choose the measure fields for line events:			
From-Measure:	From_M		
(4) - <u>T</u> o-Measure:	To_M 🗸		
Choose the offset field. Events can be offset from their routes.			
(5) <u>O</u> ffset:	Offset 🗸		
Warn me if the res	Wam me if the resulting layer will have restricted functionality		
Advanced Options	(6) Right of the route OK Cancel		

- 11. Click on Advanced Options and check **Right of the route. The side is determined by the digitized direction**. Once more, you can see how important the direction of the sketch is. Click on **OK**.
- 12. The SpeedLimit Events layer has been added. Symbolize the line route event layer based on the MaximumSpeed supplementary field: Layer Properties | Symbology | Category: Unique values.

The city speed limit for public transport is **50 km per hour** and only a speed limit of **30 km per hour** is a critical restriction. For this reason, let's update the SpeedLimits route event table by erasing the records with a maximum speed of **50 km per hour**:



- 13. Start an edit session. A warning message tells you that event layers are not editable. Point and line events are temporary layers and are stored only in your map document. Click on **Continue**.
- 14. Open the attribute table of the SpeedLimits event table. With Select by Attributes, select all line events with MaximumSpeed as 50. Click on Delete Selected to delete the selected records. Notice that line events with MaximumSpeed of 50 were deleted from the map. Use the F5 key to refresh the map. Explore the attribute table of the SpeedLimits Events layer to see changes. You can use the Undo Database Row(s) Deleted and Redo tools to better see again how your line events are updating. Rename your layer: SpeedLimits30 Events.
- 15. Save your map document as MyEevents.mxd.

You can find the results of this recipe at ... \Data \LinearReferencing\Events.

How it works...

You have stored the point and line events in separate tables. Because an event represents an attribute of the route, you can add additional information in your event table. The SpeedLimits event table contains the MaximumSpeed field that stores the maximum allowed speed for public transportation.

You have already noticed that your event table references multiple routes (for example, 79 bus line, 133 bus line) from a single route feature class.

Events with a negative Offset value will be placed on the right-hand side of the route. In this way, your bus stops that have the same location along the same route (for example, bus line 133) will be displayed on the left-hand side and the right-hand side of the route.

At step 13, you have seen that ArcGIS cannot edit the event layers. If you want to make it editable, export it as a feature class or a shape file. By exporting the event layer, the dynamic association between the event layer and the route event table will be lost.

Working with complex routes


Complex routes obey the simple route rules. Complex routes contain the close loop, selfintersecting, double-back (overlap), and branching route features.

Getting ready

In this section, you will create a delivery route for customers of the Farm Food Delivery service. Your complex route will be used for:

- ► Measurement system: time
- Measure unit: minutes

Your complex route will use the street centerlines as reference lines from the Street feature class. The complex route will have eight simple routes as shown in the following screenshot:





- Chapter 8

In the end, your complex route will form a closed loop by double backing on itself and self-intersecting.

You can continue to work in your map document MyEvents.mxd, add the FarmFoodDelivery layer, and skip step 1. Open the YourEvents.pdf file from ...\Data\LinearReferencing. The file contains all necessary information to complete the complex route.

How to do it...

Follow these steps to create a complex route in ArcMap:

- Start ArcMap and open the existing map document StartComplexRoute.mxd from <drive>:\PacktPublishing\Data \LinearReferencing\Events.
- 2. Open the **Catalog** window and expand VeloGIS.gdb from the same location. Create a new route feature class named FarmFoodDelivery_h.

The letter h should indicate the measure unit that will be used by your complex route (hours, minutes, seconds). Follow the steps from the *Creating and editing routes* recipe. Document the measurement system and measure units in your feature class metadata: Delivery service. The measurement system is time. The measure units are minutes.

- 3. Start the edit session. Prepare the editing environment as follows:
 - For List by Selection | Selectable, set Streets as the only selectable layer
 - Snapping toolbar | Options | Tolerance: 5 pixels
 - Snapping toolbar | Snapping: End, Vertex, and Edge

The YourEvents.pdf file contains the measure values for all your simple routes. You will create eight simple routes, as shown in the previous screenshot.

- 4. Let's create the first simple route. Click on the **Edit** tool and select the street feature with **OBJECTID** as 3 that will represent **Route 1**.
- 5. On the **Route Editing** toolbar, select the **Make Route** tool. Move the dialog box to see the selected feature.
- 6. From Click on the start point, select the Start Point button.
- 7. On the map, click and snap on the start point: Farm Food Delivery (point **1** on the preceding screenshot).
- 8. In the **Make Route** dialog box, select **From/To measure**, and type 0 and 7. Click on **Make Route**. Your first simple route starts from 0 minutes and ends at 7 minutes. Clear the selected feature with the **Clear Selected Feature** tool.
- 9. Create the second simple route. Select the second street with **OBJECTID** as 1 that will represent **Route 2**. Click on **Make Route** and click on *intersection 1* (or point **2** on the screenshot).



Working with Geocoding and Linear Referencing -

- 10. Type the values for **From/To measure**: 7 and 27. Click on **Make Route**. Your second simple route starts from 7 minutes and ends at 27 minutes. Continue to create the remaining routes as shown in YourEvents.pdf.
- 11. Save the edits and clear all selected features.

Let's merge all eight simple routes into a complex route:

- 12. In the **Table Of Contents** section, right-click on FarmFoodDelivery_h, and navigate to **Selection** | **Select All**. From the **Editor** menu, select **Merge**, and select the first record. Check **Preserve Overlapping segments** and click on **OK**.
- 13. On the **Editor** toolbar, select the **Attributes** tool, and for the RouteID field, enter the value 1. Save the edits.
- 14. Set FarmFoodDelivery_h as the selectable layer. Explore your route using the Edit Sketch Properties window and the Identify Route Location Results tool.
- 15. Stop the edit session. Save your map document as MyComplexRoute.mxd.

You can find the results of this recipe at ... \Data\LinearReferencing\ ComplexRoutes.

How it works...

Generally, the digitized direction of the reference feature (for example, street centerline) determines the direction of the simple route. In this recipe, you saw that the direction of the increasing measure does not have to coincide with the digitized direction of the reference feature. Assign carefully the correct measures to the simple routes that will merge. With the **Identify Route Location Results** tool, click on the double-back segment of the complex route (**Routes 6** and **Route 7** from the screenshot). You will find two route identifiers with the same **RouteID** as 1. Even if it is a single route, **Measure** will report a value for the going path and another value for the return path.

Analyzing events

Events support two overlay operations: union and intersection. The event tables or event layers can be used as input in an overlay analysis operation.

To avoid errors, respect the following conditions:


- ▶ Use the same measure system
- Measures should be incremented in the same direction and reference the same route
- Event layers should cover the same area

The result of an overlay operation is a new event table that contains the attributes from the input tables.



Getting ready

In this section, you want to identify the possible traffic jam sections generated by the speed restriction and frequent stops of the buses as shown in the following screenshot:



You can use this information to relocate some bus stops or bus lines in order to reduce traffic congestion.

You will perform a line-on-point intersection of two event tables: BusStop and SpeedLimits. Your SpeedLimits line event table contains only the section with the speed limit of **30 km per hour**. Both event tables reference the BusRoute_m route and have the same measurement system and measure unit: *distance* and *meters*.

You can continue to work in your map document MyEvents.mxd and skip step 1.

How to do it...

Follow these steps to analyze the traffic along a bus route using ArcMap:

1. Start ArcMap and open the existing map document Analyze.mxd from <drive>:\ PacktPublishing\Data\LinearReferencing\Events.



Working with Geocoding and Linear Referencing -

- Open ArcToolbox, expand Linear Referencing Tools, and double-click on the Overlay Route Events tool to open the dialog box. Set the following parameters:
 - Input Event Table: SpeedLimit_30
 - Route Identifier Field: RoadID
 - Event Type: Line
 - From-Measure Field: From M
 - □ **To-Measure Field**: To_M
 - Overlay Event Table: BusStop
 - Route Identifier Field: RoadID
 - Event Type: Point
 - □ Measure Field: Loc_M
 - **Type of Overlay:** INTERSECT
 - Output Event Table: VeloGIS.gdb\TrafficJam
 - Route Identifier Field: RoadID
 - □ Measure Field: Loc_M
- 3. Click on **OK**. Open the TrafficJam table to examine the result. Your event table now has the location along the route and the speed value.
- 4. Let's create a point route event layer based on the TrafficJam table. In **ArcToolbox**, go to **Linear Referencing Tools**, and double-click on the **Make Route Event Layer** tool to open the dialog box. Set the following parameters:
 - Input Route Feature: BusRoutes
 - Route Identifier Field: RoadID
 - Input Event Table: VeloGIS.gdb\TrafficJam
 - Route Identifier Field: RoadID
 - Event Type: Point
 - □ Measure Field: Loc_M
 - Layer Name or Table View: TrafficJam Events
 - Offset Field: none
- 5. Leave all other options unchecked. Click on **OK**. The TrafficJam Events layer has been added in the **Table Of Contents** section.

242

6. Open the TrafficJam Events layer table to examine the result. Right-click on the RouteID field and select **Summarize**. For **Select a field to summarize**, select RouteID. For Specify output table, go to your geodatabase, and save the table as Sum_TrafficJam. Click on **Yes** to add the table in the **Table Of Contents** section. Open the Sum TrafficJam table to examine the results.

It seems that route 79 has the highest bus stop count in the speed restriction zone. The locations of Route 133: 41 and Route 79:92 refer to the same location on Dacia Avenue. There are double stops for bus 79 and 133 and this could generate a traffic jam in the area.

7. Save your map document as MyAnalyze.mxd.

You can find the results of this recipe at ... $\$ LinearReferencing Analyze.

How it works...

The line-on-point intersection returned an output table with attributes from both the input and overlay tables, as follows:

- ▶ The RouteID field
- ► The Loc M field-point locations along the route from the BusStop event table
- ► The MaximumSpeed optional field from the SpeedLimit_30 event table

Based on the output table, you created a new point event layer. If you want to save it as a feature class in your geodatabase, right-click on the TrafficJam Events layer, and go to **Data | Export Data**.

243

In this chapter, we will cover the following recipes:

- Analyzing surfaces
- Interpolating data
- Reclassifying a raster
- Working with Map Algebra
- Working with Cell Statistics
- ► Generalizing a raster
- Creating density surfaces
- Analyzing the least-cost path

Introduction

The **ArcGIS Spatial Analyst** extension offers a lot of great tools for geoprocessing raster data. Most of the *Spatial Analyst* tools generate a new raster output. Before starting a raster analysis session, it's best practice to set the main analysis environment parameters settings (for example, scratch the workspace, extent, and cell size of the output raster). In this chapter, you will store all raster datasets in file geodatabase as **file geodatabase raster datasets**.



For theoretical aspects about spatial data analysis, please refer to Geographic Information Analysis, David O'Sullivan and David Unwin, John Wiley & Sons, Inc., 2003.

For more details about the Spatial Analyst toolbox, please refer to ArcG/S Help(10.2) at http://resources.arcgis.com/en/help/main/10.2 online.

Analyzing surfaces

In this recipe, you will represent 3D surface data in a two-dimensional environment. To represent 3D surface data in the ArcMap 2D environment, you will use hillshades and contours. You can use the hillshade raster as a background for other raster or vector data in ArcMap.

Using the surface analysis tools, you can derive new surface data, such as slope and aspect or locations visibility.

Getting ready

In the surface analysis context:

- The term slope refers to the steepness of raster cells
- Aspect defines the orientation or compass direction of a cell
- > Visibility identifies which raster cells are visible from a surface location

In this recipe, you will prepare your data for analysis by creating an elevation surface named Elevation from vector data. The two feature classes involved are the PointElevation point feature class and the ContourLine polyline feature class. All other output raster datasets will derive from the Elevation raster.

How to do it...

Follow these steps to prepare your data for spatial analysis:

1. Start ArcMap and open the existing map document, SurfaceAnalysis.mxd, from
 <drive>:\PacktPublishing\Data\SpatialAnalyst. Go to Customize |
 Extensions and check the Spatial Analyst extension.

246

- 2. Open **ArcToolbox**, right-click on the **ArcToolbox** toolbox, and select **Environments**. Set the geoprocessing environment as follows:
 - Workspace | Current Workspace: Data\SpatialAnalyst\ TOP05000.gdb and Scratch Workspace: Data\SpatialAnalyst\ ScratchTOP05000.gdb.
 - Output Coordinates: Same as Input.
 - **Raster Analysis | Cell Size: As Specified below:** type 0.5 with unit as **m**.
 - □ **Mask**: SpatialAnalyst\TOPO5000.gdb\Trapezoid5k.
 - Raster Storage | Pyramid: check Build pyramids and Pyramid levels: type
 Click on OK.
- 3. In ArcToolbox, expand Spatial Analyst Tools | Interpolation, and double-click on the Topo to Raster tool to open the dialog box. Click on Show Help to see the meaning of every parameter. Set the following parameters:
 - Input feature data:

PointElevation Field: Elevation and Type: PointElevation

ContourLine Field: Elevation and Type: Contour

WatercourseA Type: Lake

- Output surface raster: ... ScratchTOPO5000.gdb\Elevation
- Output extent (optional): ContourLine
- Drainage enforcement (optional): NO ENFORCE
- 4. Accept the default values for all other parameters. Click on **OK**. The Elevation raster is a *continuous thematic raster*. The raster cells are arranged in 4,967 rows and 4,656 columns.
- Open Layer Properties | Source of the raster and explore the following properties: Data Type (File Geodatabase Raster Dataset), Cell Size (0.5 meters) or Spatial Reference (EPSG: 3844).
- 6. In the Layer Properties window, click on the Symbology tab. Select the Stretched display method for the continuous raster cell values as follows: Show: Stretched and Color Ramp: Surface. Click on OK.



- 7. Explore the cell values using the following two options:
 - Go to Layer Properties | Display and check Show MapTips
 - Add the Spatial Analyst toolbar, and from Customize | Commands, add the Pixel Inspector tool

Let's create a hillshade raster using the Elevation layer:


- 8. Expand **Spatial Analyst Tools** | **Interpolation** and double-click on the **Hillshade** tool to open the dialog box. Set the following parameters:
 - □ **Input raster**: ScratchTOPO5000.gdb\Elevation
 - **Output raster**: ScratchTOPO5000.gdb\Hillshade
 - Azimuth (optional): 315 and Altitude (optional): 45
- 9. Accept the default value for **Z factor** and leave the **Model shadows** option unchecked. Click on **OK**.

From time to time, please ensure to save the map document as MySurfaceAnalysis.mxd at ...\Data\SpatialAnalyst.

- 10. The Hillshade raster is a discrete thematic raster that has an associated attribute table known as Value Attribute Table (VAT). Right-click on the Hillshade raster layer and select Open Attribute Table.
- 11. The Value field stores the illumination values of the raster cells based on the position of the light source. The 0 value (black) means that 25406 cells are not illuminated by the sun, and 254 value (white) means that 992 cells are entirely illuminated. Close the table.
- 12. In the **Table Of Contents** section, drag the Hillshade layer below the Elevation layer, and use the **Effects** | **Transparency** tool to add a transparency effect for the Elevation raster layer, as shown in the following screenshot:

248

Chapter 9




In the next step, you will derive a raster of slope and aspect from the Elevation layer.

- 13. Expand **Spatial Analyst Tools** | **Interpolation** and double-click on the **Slope** tool to open the dialog box. Set the following parameters:
 - Input raster: Elevation
 - Output raster: ScratchTOPO5000.gdb\SlopePercent
 - Output measurement (optional): PERCENT_RISE

249—

14. Click on **OK**. Symbolize the layer using the Classified method, as follows: Show: Classified. In the **Classification** section, click on **Classify** and select the **Manual** classification method. You will add seven classes. To add break values, right-click on the empty space of the **Insert Break** graph. To delete one, select the break value from the graph, and right-click to select **Delete Break**. Do not erase the last break value, which represents the maximum value. Secondly, in the **Break Values** section, edit the following six values: 5; 7; 15; 20; 60; 90, and leave unchanged the seventh value (496, 6). Select Slope (green to red) for **Color Ramp**. Click on **OK**. The green areas represent flatter slopes, while the red areas represent steep slopes, as shown in the following screenshot:



- 15. Expand **Spatial Analyst Tools** | **Interpolation** and double click on the **Aspect** tool to open the dialog box. Set the following parameters:
 - Input raster: Elevation
 - Output raster: ScratchTOPO5000.gdb\Aspect
- 16. Click on **OK**. Symbolize the Aspect layer. For **Classify**, click on the **Manual** classification method. You will add *five classes*. To add or delete break values, rightclick on the empty space of the graph, and select **Insert / Delete Break**. Secondly, edit the following four values: 0; 90; 180; 270, leaving unchanged the fifth value in the **Break Values** section. Click on **OK**.



- Aspect Slope Direction Flat cells North-East East-South South-West West-North
- 17. In the **Symbology** window, edit the labels of the five classes as shown in the following picture. Click on **OK**. In the **Table Of Contents** section, select the **<VALUE>** label, and type Slope Direction. The following screenshot is the result of this action:

In the next step, you will create a raster of visibility between two geodetic points in order to plan some topographic measurements using an electronic theodolite. You will use the TriangulationPoint and Elevation layers:

18. In the **Table Of Contents** section, turn on the TriangulationPoint layer, and open its attribute table to examine the fields.

There are two geodetic points with the following supplementary fields: OffsetA and OffsetB. OffsetA is the proposed height of the instrument mounted on its tripod above stations 8 and 72. OffsetB is the proposed height of the reflector (or target) above the same points.

- 19. Close the table. Expand **Spatial Analyst Tools** | **Interpolation** and double-click on the **Visibility** tool to open the dialog box. Click on **Show Help** to see the meaning of every parameter. Set the following parameters:
 - Input raster: Elevation
 - Input point or polyline observer features: TOPO5000.gdb\ GeodeticPoints\TriangulationPoint
 - **Output raster:** ScratchTOPO5000.gdb\Visibility
 - Analysis type (optional): OBSERVERS




- Observer parameters | Surface offset (optional): OffsetB
- Observer offset (optional): OffsetA
- **Outer radius (optional):** For this, type 1600

Notice that OffsetA and OffsetB were automatically assigned. The **Outer radius** parameter limits the search distance, and it is the rounded distance between the two geodetic points. All other cells beyond the 1,600-meter radius will be excluded from the visibility analysis.

20. Click on OK. Open the attribute table of the <code>Visibility</code> layer to inspect the fields and values.

The Value field stores the value of cells. Value 0 means that cells are not visible from the two points. Value 1 means that 6, 608, 948 cells are visible only from point 8 (first observer OBS1). Value 2 means that 1, 813, 578 cells are visible only from point 72 (second observer OBS2). Value 3 means that 4, 351, 861 cells are visible from both points. In conclusion, there is visibility between the two points if the height of the instrument and reflector is 1.5 meters. Close the table.

21. Symbolize the Visibility layer, as follows: Show: Unique Values and Value Field: Value. Click on Add All Values and choose Color Scheme: Yellow-Green Bright. Select <Heading> and change the Label value to Height 1.5 meters. Double-click on the symbol for Value as 0, and select No Color. Click on OK. The Visibility layer is symbolized as shown in the following screenshot:





22. Turn off all layers except the Visibility, TriangulationPoint, and Hillshade layers. Save your map as MySurfaceAnalysis.mxd and close ArcMap.

You can find the final results at <drive>:\PacktPublishing\Data\SpatialAnalyst\ SurfaceAnalysis.

How it works...

You have started the exercise by setting the geoprocessing environment. You will override those settings in the next recipes. At the application level, you chose to build pyramids. By creating pyramids, your raster will be displayed faster when you zoom out. The pyramid levels contain the copy of the original raster at a low resolution. The original raster will have a cell size of 0.5 meters. The pixel size will double at each level of the pyramid, so the first level will have a cell size of 1 meter; the second level will have a cell size of 2 meters; and the third level will have a cell size of 4 meters.

Even if the values of cells refer to heights measured above the local mean sea level (zero-level surface), you should consider the planimetric accuracy of the dataset. Please remember that TOPO5000.gdb refers to a product at the scale 1:5,000. This is the reason why you have chosen 0.5 meters for the raster cell size. At step 4, you used the PointElevation layer as supplementary data when you created the Elevation raster.

If one of your **ArcToolbox** tools fails to execute or you have obtained an empty raster output, you have some options here:

 Open the **Results** dialog from the **Geoprocessing** menu to explore the error report. This will help you to identify the parameter errors. Right-click on the previous execution of the tool and choose **Open** (step 1). Change the parameters and click on **OK** to run the tool. Choose **Re Run** if you want to run the tool with the parameters unchanged (step 2) as shown in the following screenshot:

Results		🗆 ×
🖃 🛅 Current Session		~
🗉 🕱 IDW		
 ○ DW [1205 ○ Outpu ○ Outpu ○ Inputs ○ Inputs ○ Enviro ↓ Ex ↓ Ex ↓ Ex ↓ St ○ ER ★ ○ Th ○ A ○ A ○ Th ○ No spat ○ The geo ○ ERROR ○ ERROR ○ ERROR 	Open (1) Copy Remove Rename Copy As Python Snippet Delete Re Run (2) Share As Save As Ial reference exists. Imetry is not M-aware 010062: Error in executing grid 010017: Operation has been ca o execute (Idw).	
C Esilad a	FTue Cee 14 19:00:94 9014 /El-	second Time



 Run the ArcToolbox tool from the ArcCatalog application. Before running the tool, check the geoprocessing environment in ArcCatalog by navigating to Geoprocessing | Environments.

There's more...

In *Chapter 4*, *Geoprocessing*, you learned to work with **Model Builder**. What if you have a model with all previous steps?

Open ArcCatalog, and go to ...Data\SpatialAnalyst\ModelBuilder. In the ModelBuilder folder, you have a toolbox named MyToolbox, which contains the **Surface Analysis** model. Right-click on the model and select **Properties**. Take your time to study the information from the **General**, **Parameters**, and **Environments** tabs. The output (derived data) will be saved in **Scratch Workspace**: ModelBuilder\ ScratchTopo5000.gdb. Click on **OK** to close the **Surface Analysis Properties** window. Running the entire model will take you around 25 minutes. You have two options:

- ► **Tool dialog option**: Right-click on the **Surface Analysis** model and select **Open**. Notice the model parameters that you can modify and read the **Help** information. Click on **OK** to run the model.
- Edit mode: Right-click on the Surface Analysis model and select Edit. The colored model elements are in the second state—they are ready to run the Surface Analysis model by using one of those two options:
 - To run the entire model at the same time, select Run Entire Model from the Model menu.
 - To run the tools (yellow rounded rectangle) one by one, select the Topo to Raster tool with the Select tool, and click on the Run tool from the Standard toolbar. Please remember that a shadow behind a tool means that the model element has already been run.

You used the **Visibility** tool to check the visibility between two points with 1.5 meters for the **Observer offset** and **Surface offset** parameters. Try yourself to see what happens if the offset value is less than 1.5 meters. To again run the **Visibility** tool in the **Edit** mode, right-click on the tool, and select **Open**. For **Surface offset** and **Observer offset**, type 0.5 meters and click on **OK** to run the tool. Repeat these steps for a 1 meter offset.

See also

 If you want to determine the visibility between two or more points using other great tools, please refer to the Intervisibility recipe in Chapter 10, Working with 3D Analyst

254

Interpolating data

Spatial interpolation is the process of estimating an unknown value between two known values taking into account Tobler's First Law:

"Everything is related to everything else, but near things are more related than distant things."

This recipe does not undertake to teach you the advanced concept of interpolation because it is too complex for this book. Instead, this recipe will guide you to create a terrain surface using the following:

- A feature class with sample elevation points
- Two interpolation methods: Inverse Distance Weighted (IDW) and Spline



For further research, please refer to: Geographic Information Analysis, David O'Sullivan and David Unwin, John Wiley & Sons, Inc., 2003, specifically the 8.3 Spatial interpolation recipe of Chapter 8, Describing and Analyzing Fields, pp.220-234.

Getting ready

In this recipe, you will create a terrain surface stored as a raster using the PointElevation sample points. Your sample data has the following characteristics:

- The average distance between points is 150 meters
- The density of sample points is not the same on the entire area of interest
- There are not enough points to define the cliffs and the depressions
- There are not extreme differences in elevation values

How to do it...

Follow these steps to create a terrain surface using the **IDW** tool:

- Start ArcMap and open an existing map document Interpolation.mxd from <drive>:\PacktPublishing\Data\SpatialAnalyst.
- 2. Set the geoprocessing environment, as follows:
 - Workspace | Current Workspace: Data\SpatialAnalyst\ TOPO5000.gdb and Scratch Workspace: Data\SpatialAnalyst\ ScratchTOPO5000.gdb




- **Output Coordinates:** Same as the PointElevation layer
- Raster Analysis | Cell Size: As Specified Below: 1
- **Mask**: Data\SpatialAnalyst\TOPO5000.gdb\Trapezoid5k

In the next two steps, you will use the **IDW** tool. Running **IDW** with barrier polyline features will take you around 15 minutes:

- 3. In **ArcToolbox**, go to **Spatial Analyst Tools** | **Interpolation**, and double-click on the **IDW** tool. Click on **Show Help** to see the meaning of every parameter. Set the following parameters:
 - Input point features: PointElevation
 - **Z value field**: Elevation
 - Output raster: ScratchTOPO5000.gdb\IDW_1
 - **Power (optional):** 0.5
 - Search radius (optional): Variable
 - Search Radius Settings | Number of points: 6
 - **Maximum distance**: 500
 - Input barrier polyline features (optional): TOPO5000.gdb\Hydrography\
 WatercourseL
- 4. Accept the default value of **Output cell size (optional)**. Click on **OK**.
- 5. Repeat step 3 by setting the following parameters:
 - Input point features: PointElevation
 - **Z value field**: Elevation
 - **Output raster**: ScratchTOPO5000.gdb\IDW_2
 - **Power (optional):** 2

256

6. The rest of the parameters are the same as in step 3. Click on OK. Symbolize the IDW_1 and IDW_2 layers as follows: Show: Classified; Classification: Equal Interval: 10 classes; Color Scheme: Surface. Click on OK. You should obtain the following results:



In the following steps, you will use the **Spline** tool to generate the terrain surface:

- 7. In **ArcToolbox**, go to **Spatial Analyst Tools** | **Interpolation**, and double-click on the **Spline** tool. Set the following parameters:
 - Input point features: PointElevation
 - **Z value field**: Elevation
 - **Output raster**: ScratchTOPO5000.gdb\Spline Regular
 - **Spline type (optional):** REGULARIZED
 - Weight (optional): 0.1 and Number of points (optional): 6
- 8. Accept the default value of **Output cell size (optional)**. Click on **OK**.
- 9. Run again the **Spline** tool with the following parameters:
 - Input point features: PointElevation
 - **Z value field**: Elevation
 - **Output raster**: ScratchTOPO5000.gdb\Spline_Tension
 - **Spline type (optional)**: TENSION
 - Weight (optional): 0.1 and Number of points (optional): 6



- Spline Type:Regularized
- 10. Accept the default value of **Output cell size (optional)**. Click on **OK**. Symbolize the Spline_Regular and Spline_Tension raster layers using the **Equal Interval** method classification with 10 classes and the Surface color ramp:


In the next steps, you will use the **Spline** with **Barriers** tool to generate a terrain surface using an increased number of sample points. You will transform the ContourLine layer in a point feature class. You will combine those new points with features from the PointElevation layer:

- 11. In **ArcToolbox**, go to **Data Management Tools** | **Features**, and double-click on the **Feature vertices to Points** tool. Set the following parameters:
 - Input features: ContourLine
 - Output Feature Class: TOPO5000.gdb\Relief\ ContourLine_ FeatureVertices
 - Point type (optional): ALL
- 12. Click on **OK**. Inspect the attribute table of the newly created layer. In the **Catalog** window, go to ... TOPO5000.gdb\Relief and create a copy of the PointElevation feature class. Rename the new feature class as ContourAndPoint. Right-click on ContourAndPoint and select **Load** | **Load Data**. Set the following parameters from the second and fourth panels:
 - Input data: ContourLine_FeatureVertices
 - Target Field: Elevation
 - Matching Source Field: Elevation

13. Accept the default values for the rest of the parameters and click on Finish.



- 14. In ArcToolbox, go to Spatial Analyst Tools | Interpolation, and double-click on the Spline with Barriers tool. Set the following parameters:
 - Input point features: ContourAndPoint
 - **Z value field**: Elevation
 - Input barrier features (optional): TOPO5000.gdb\Hydrography\ WatercourseA
 - Output raster: ScratchTOPO5000.gdb\Spline WaterA
 - **Smoothing Factor (optional)**: 0
- 15. Accept the default value of **Output cell size (optional)**. Click on **OK**. You should obtain a similar terrain surface to what's shown here:



Explore the results by comparing the similarities or differences of the terrain surface between interpolated raster layers and the ContourLine vector layer. The IDW method works well with a proper density of sample points. Try to create a new surface using the **IDW** tool and the ContourAndPoint layer as sample points.

16. Save your map as MyInterpolation.mxd and close ArcMap.

You can find the final results at <drive>:\PacktPublishing\Data\SpatialAnalyst \ Interpolation.

How it works...

The IDW method generated an average surface that will not cross through the known point elevation values and will not estimate the values below the minimum or above the maximum given point values. The **IDW** tool allows you to define polyline barriers or limits in searching sample points for interpolation. Even if the WatercourseL polyline feature classes do not have elevation values, river features can be used to interrupt the continuity of interpolated surfaces.



To obtain fewer averaged estimated values (reduce the IDW smoother effect) you have to:

- ► Reduce the sample size to 6 points
- Choose a variable search radius
- ▶ Increase the power to 2

The **Power** option defines the influence of sample point values. This value increases with the distance. There is a disadvantage because around a few sample points, there are small areas raised above the surrounding surface or small hollows below the surrounding surface.

The **Spline** method has generated a surface that crosses through all the known point elevation values and estimates the values below the minimum or above the maximum sample point values. Because the density of points is quite low, we reduced the sample size to **6** points and defined a variable search radius of 500 meters in order to reduce the smoothening effect.

The **Regularized** option estimates the hills or depressions that are not cached by the sample point values. The **Tension** option will force the interpolated values to stay closer to the sample point values.

Starting from step 12, we increased the number of sample points in order to better estimate the surface. At step 14, notice that the **Spline with Barriers** tool allows you to use the polygon feature class as breaks or barriers in searching sample points for interpolation.

Reclassifying a raster

When you reclassify a raster, you reassign one or more cell values or a range of values to new output cell values. You may need to reclassify a raster to:

- Update the cell values with new information from the field
- Simplify raster data
- Add cell values to a common scale
- Exclude values from analysis by setting those values to NoData
- Include NoData cells in analysis by setting values to those cells

The classification method and the number of classes you define will affect the raster displaying and interpreting process.

Getting ready

In this recipe, you will add the cell values to a common scale for three thematic raster layers: LandUse, SlopeProcent, and Aspect.



How to do it...

Follow these steps to reclassify three raster layers:

- 1. Start ArcMap and open a new map document. Add the following datasets to the map:
 - The LandUse feature class from ...Data\SpatialAnalyst\ TOPO5000.gdb\LandUse
 - The Elevation, SlopeProcent, and Aspect rasters from SpatialAnalyst\ScratchTOPO5000.gdb
- 2. Save your map as ReclassifyRaster.mxd. Load the **Spatial Analyst** extension and set the analysis environment, as you learned in the previous recipe.

Firstly, you will convert the LandUse vector layer in a discrete thematic raster with a cell size of 0.5 meters:

- 3. In **ArcToolbox**, expand **Conversion Tools** | **To Raster**, and double-click on the **Polygon to Raster** tool to open the dialog box. Set the following parameters:
 - Input Features: LandUse
 - Value Field: CAT
 - Output Raster Dataset: ... ScratchTOPO5000.gdb\LandUse
 - Cell assignment type (optional): MAX_AREA
- 4. Accept the default values for all other parameters. Click on **OK**. Add the LandUse raster to your map.
- 5. Right-click on the LandUse raster layer and select **Properties** | **Symbology**. For the Unique Values display, change **Color Schema** to Terra Tones. Select the Black color for **Display NoData as**. Click on **OK**.
- 6. A discrete raster has associated an attribute table named the Value Attribute Table (VAT). Open its Value Attribute Table. The **Value** field stores the subtype codes from the input LandUse vector layer. You worked with that code in the *Creating subtypes* recipe of *Chapter 1*, *Designing Geodatabase*.

261

In the next steps, you will manually reclassify the cell values of the LandUse raster layer, as shown in the following table:

CAT Description: Category	Code	New cell values	CAT Description: Category	Code	New cell values
Hydrography	31	NoData	Forest	21	4
Transportation	41				
Arable	11	3	Vineyard	14	5
Fruit orchard	15		Other terrains	42	
Pasture	12	1	Unproductive	51	2
Meadow	13				

- 7. In **ArcToolbox**, expand **Spatial Analyst Tools** | **Reclass**, and double-click on the **Reclassify** tool to open the dialog box. Set the following parameters:
 - Input Raster: LandUse
 - Reclass field: Value
 - Reclassification: For this, click on the Unique button to see all values
- 8. You will delete the Hydrography and Transportation values. Press the *Ctrl* key, and select the small box to the left of the rows with old values as 31 and 41. The rows will become yellow. Click on **Delete Entries**. You will modify the values of the **New cell values** column as shown in the preceding table; for example, the old value 11 will have the new value as 4.
- 9. After you finish adding all new values, click on the **Save** button to save the values in a *remap table* (information table) named ReclassLU. You can reuse this information table if you want to repeat the step.
- 10. Continue to set the last two parameters:
 - Output Raster: ... ScratchTOPO5000.gdb\ReclassLU
 - Check Change missing values to NoData (optional)
- 11. Click on OK. Add the ReclassLU raster to your map. Right-click on the raster layer and select Properties | Symbology. For the Unique Values display, change Color Schema to Yellow-Green bright. Click on the Symbols column to select Flip Colors. For Display NoData as, select Black. Click on OK.
- 12. Open the ReclassLU raster attribute table to inspect the result.



- 13. Turn off all layers except the SlopeProcent raster layer. In **ArcToolbox**, expand **Spatial Analyst Tools** | **Reclass**, and double-click on the **Reclassify by Table** tool to open the dialog box. Set the following parameters:
 - Input Raster: SlopePercent
 - Input remap table: Data\SpatialAnalyst\ReclassifySlopePercent
 - **From value field**: FROM
 - **D** To value field: TO
 - Output value field: NewValue
 - Output Raster: ... ScratchTOPO5000.gdb\ReclassSlope
 - Check Change missing values to NoData (optional)
- 14. Click on **OK**. Add the Reclasslope raster to your map. Symbolize the raster as follows: **Unique Values** display method, **Color Schema**: Slope, and **Display NoData as**: Black.

In the next step you will reclassify the cell values of the Aspect raster layer:

15. Turn off all layers except the Aspect raster layer. In **ArcToolbox**, expand **Spatial Analyst Tools** | **Reclass**, and double-click on the **Reclassify** tool to open the dialog box. Set the following new values:

Old values	New values
	3
0 - 90	2
90 - 180	1
180 - 270	1
270 - 359,999237	5
NoData	NoData

- 16. Add the ReclassAspect raster to your map. Symbolize the raster as follows: Unique Values display method, Color Schema: Red to Green, Flip colors, and Display NoData as: Black.
- 17. Save your map and close ArcMap.

You can find the final results at <drive>:\PacktPublishing\Data\SpatialAnalyst\ Reclassify.

263—

How it works...

This is how these steps work:

- ► At step 5, you saw NoData for the LandUse raster layer. The surface from the LandUse feature class follows the trapezoid shape of the scanned map. Your output LandUse raster is a grid of square cells (4,967 rows and 4,656 columns).
- ► At step 8, you set NoData for the Hydrography and Transportation cell values in order to exclude them from future analysis.

The *reclassification range* is common for all three raster layers: *from 1* to 5. The value 1 means the most suitable value, while the value 5 means the least suitable value.

There's more...

Let's suppose we want to find the best places for fruit orchards by overlaying the following rasters: ReclassLU, ReclassSlope, and ReclassAspect. In our scenarios, we are searching the Pasture, Meadow, or Unproductive surface with slope range value from 7 percent, to 15 percent and direction range from southeast to southwest.

In the next steps, you will find suitable places for the fruit orchards using weight raster layers:

- Open the last saved map document, ReclassifyRaster.mxd. In ArcToolbox, expand Spatial Analyst Tools | Overlay and double-click on the Weighted Overlay tool.
- 2. For the **Evaluation** scale, select 1 to 5 by 1 from the drop-down list.
- Click on the Add raster row button to add ReclassLU, ReclassSlope, and ReclassAspect. Field contains the reclassified values of the LandUse raster, and Scale Value refers to the ranking of suitability. Be sure those columns have the same values.

Define the percent of influence for all raster layers.

- 4. Assign to ReclassLU an influence of 50 percent, to ReclassSlope an influence of 30 percent, and to ReclassAspect an influence of 20 percent. Set Output raster: ...ScratchTOPO5000.gdb\Fruit_Orchards. Click on OK. Open its Fruit_Orchards attribute table to inspect the result. There are only three cells with value 1, which represent the most suitable surface.
- 5. Save your map and close ArcMap.



Thus, we conclude this:

- We didn't find the most suitable surface with value 1—appropriate land use, slope, and aspect for a fruit orchard
- We obtained a reasonable alternative value 2

Working with Map Algebra

Map Algebra is the math for raster datasets. The math-like expressions contain operators (for example, Divide, Equal To, And, Over, and InList) and functions (for example, Mean, Con, Slope, and Aspect).

Some Map Algebra operators and functions return logical values: True (logical value 1) and False (logical value 0). Be aware of NoData cell values because Map Algebra will not interpret this nonzero value as a true condition.

Getting ready

In this recipe, you will use Map Algebra expressions to identify the suitable sites for fruit orchards and reforestation. You will update the LandUse raster dataset with the proposed forest and fruit orchard sites using a Map Algebra operator called Over.

How to do it...

Follow these steps to learn how to work with Map Algebra:

- 1. Start ArcMap and open the existing map document MapAlgebra.mxd from: <drive>:\PacktPublishing\Data\SpatialAnalyst.
- 2. Add the following rasters created in the *Reclassifying a raster* recipe: ReclassAspect and LandUse. Load the **Spatial Analyst** extension and set the analysis environment. In the **Table Of Contents** section, turn off all layers except SlopePercent.

In the next step, you will convert the floating point slope value to an integer value:

265

3. In ArcToolbox, expand Spatial Analyst Tools | Map Algebra and double-click, the Raster Calculator tool to open the dialog box, as shown in the following screenshot:

* Raster Calculator				
Map Algebra expression Slope_Forest Slope_Fruit Slope_Integer LandUse Aspect SlopePercent(2) HillShade Int("SlopePercent")	7 8 9 4 5 6 1 2 3 0 .	/ == != & * >>= - < <= ^ + () ~	Math Abs Exp Exp 10 Exp2 Float Int (1)	• III •
Output raster (3)	\SpatialAnal	lyst\ScratchTOPO5000. Cancel Environ		elp >>

- 4. Double-click on the Int operator to start building the expression. Move the cursor into the brackets and double-click on the SlopePercent layer. Rename the **Output raster**: ScratchTOPO5000.gdb\Slope Integer. Click on **OK**.
- 5. Explore the value attribute table of the Slope_Integer raster layer.

You will create a new raster with slope percent equal to or greater than 15 percent:

- 6. Reopen the Raster Calculator tool. Set the following parameters:
 - Build the following expression: "Slope Integer">= 15
 - Output raster: ScratchTOPO5000.gdb\Slope Forest
- 7. Click on **OK**. Open its value attribute table to inspect the fields and values. The cells with a slope value equal to or greater than 15 percent have the logical value 1 or true. Cells with other values have the logical value 0 or false.
- 8. You will create a new raster with slope percent from 7 to 14. Open the **Raster Calculator** tool. Set the following:
 - Build the following expression:
 - InList("Slope_Integer", [7,8,9,10,11,12,13,14])
 - Output raster: ScratchTOPO5000.gdb\Slope_Fruit

266

- 9. Click on **OK**. Open its value attribute table to inspect the fields and values. The raster cells have values from 7 to 14. All other cells are assigned NoData, which means there is no assigned (or recorded) value. Please remember that NoData does not mean zero value.
- 10. For Display NoData as, select the Black color to see the cells with NoData.
- 11. You will extract from the LandUse raster only Arable, Pasture, and Meadow land use types. Open the **Raster Calculator** tool. Set the following:
 - Build the following expression:

```
InList("LandUse",[11, 12,13])
```

- Output raster: ScratchTOPO5000.gdb\LandUse_Good
- 12. Click on **OK**. Open the value attribute table to inspect the fields and values. For **Display NoData as**, select the Black color to see the cells with NoData.

You will identify areas suitable for fruit orchards by putting together LandUse_Good and Slope_Fruit using the **Boolean And** tool from **Spatial Analyst Tools | Math |** Logical Toolset.

13. Open the **Boolean And** tool and set the parameters, as shown in the following screenshot:

N Boolean And		
Input raster or constant value 1	^	Boolean And
LandUse_Good 🔹 🖻		Performs a Boolean And
Input raster or constant value 2		operation on the cell values of
Slope_Fruit Output raster		two input rasters.
\SpatialAnalyst\ScratchTOPO5000.gdb\Fruit_Orchard		If both input values are true
_	_	(non-zero), the output value is 1. If one or both inputs are
4 [] >		false (zero), the output is 0. 🖕
OK Cancel Environments << Hide Help		Tool Help

14. Click on **OK**. Open the value attribute table to inspect the fields and values. The cells with the logical true value 1 refer to the area suitable for a fruit orchard. All other cells are assigned NoData.

In the previous recipe, we have identified other important criteria: direction of slope and aspect of cells. The ReclassAspect cells already have integer values because they were reclassified. Let's use the **Combinatorial And** tool to add the corresponding cell values from the ReclassAspect raster to the value attribute table of Fruit_ Orchard. This will be equivalent to geoprocessing the overlay tool for vector datasets.



15. In **ArcToolbox**, expand **Spatial Analyst Tools** | **Math** | **Logical**, and double-click on the **Combinatorial And** tool to open the dialog box. Set the following parameters:

Combinatorial And		
Input raster or constant value 1	Â	Combinatorial And
FruitOrchard Image: Constant value 2 Input raster or constant value 2 ReclassAspect	ш	Performs a Combinatorial And operation on the cell values of two input rasters.
Output raster 'a\\$cratchTOPO5000.gdb\FO_Aspect	÷	If both input values are true (non-zero), the output is a different value for each unique combination of input values. If one or both inputs are false (zero), the output value is
Cancel Environments		0. Tool Help

- 16. Click on **OK**. Open the FO_Aspect value attribute table to inspect the fields and values.
- 17. You will update the LandUse raster with the proposed fruit orchard sites using a conditional if-else function. Open the **Raster Calculator** tool. Set the following:
 - Build the following expression:

Con(IsNull("FO_Aspect"),"LandUse", 100)

- Output raster: ScratchTOPO5000.gdb\LandUse_1
- 18. Click on **OK**. Open the value attribute table to inspect the fields and values.

In the next steps, you will identify the suitable sites for reforestation by putting together LandUse Good and Slope Forest:

- 19. Open the Raster Calculator tool. Set the following:
 - Build the following expression:

"LandUse_Good" & "Slope_Forest"

- Output raster: ScratchTOPO5000.gdb\Reforestation
- 20. Click on **OK**. Open the value attribute table to inspect the fields and values. The cells with the logical true value 1 refer to the area that should be reforested.
- 21. You should also update the LandUse_1 raster with the proposed forest sites using the Over operator. This operator will paste the Reforestation value 1 over the corresponding cells in the LandUse_1 raster. The value 0 will be replaced by the corresponding cell values in the LandUse_1 raster. The NoData cell from Reforestation will be transferred to the LandUse_1 raster. For this reason, we don't want to have NoData cells in the Reforestation raster.

268

- 22. Firstly, we have to change the NoData cells to 0. You have two main options:
 - A shortcut: Open the Reclassify tool and set the following new values: Input Raster: Reforestation

Reclass field: Value

Old values	New values
0	0
1	101
NoData	0

Output raster: ScratchTOPO5000.gdb\Reclass Forest

Don't check Change missing values to NoData (optional)


• Follow the next steps using the **Raster Calculator** dialog::

```
Step 1: IsNull ("Reforestration") and Output raster: ForestNoData
```

```
Step 2: Con("ForestNoData"= =0, "Reforestation", 0) and Output
raster: Forest Final
```

Step 3: Con("Forest_Final"= =1,101,0); and Output raster:
ForestReclass

- 23. Open the **Raster Calculator** tool and build the following expression: Over("Reclass Forest", "LandUse 1").
- 24. Change the **Output raster**: ScratchTOPO5000.gdb\LandUse_Update. Click on **OK**. You should obtain a raster similar to the one shown in the following screenshot:





25. Symbolize the layer as shown in the following screenshot:

Layer Properties	A	2	-		×
General Source Extent	Display	Symbology Field	ds Joins & Relates		
Show: Unique Values	Draw ras	ter assigning a	color to each value		
Classified Stretched Discrete Color	Value Fie	ld	Color Scheme		
	Value		 Pastel Terra Tones 	•	
	Symbol	<value></value>	Label	Count 🔺	
		15	Fruit Orchard	329901	
		21	Forest	5901179	
		31	Hydrography	101966	
		41	Transportation	359649	
		42	Other Terrain	1535398	
		51	Unproductive New Fruit Orchard	10051	
		100 101		955105 460736	
		101	New Forest	400730	
	Add	l All Val <u>u</u> es	Add <u>V</u> alues	Remove	
	Def	ault C <u>o</u> lors]		
About symbology	0	olormap -	Display <u>N</u> oDat	ta as 🗾 🚽	
			·		
			ОК	Cancel Apply	

26. For **Label**, use the code description of the land use subtypes from the table presented in the *Reclassifying a raster* recipe. Set the layer transparency to 40 percent. Turn off all layers except the Hillshade and LandUse_Update raster layers. Save your map and close ArcMap.

You can find the results at <drive>:\PacktPublishing\Data\SpatialAnalyst\ MapAlgebra.

How it works...

At step 15, you created the FO_Aspect raster that contains the proposed areas for fruit orchards. To update the LandUse raster with the proposed fruit orchard sites, you built the following expression at step 17: $Con(IsNull("FO_Aspect"), "LandUse", 100)$.

```
The Con syntax is Con (<condition>, <true_expression>, {false_
expression}).
```



The expression means *if* (a cell from FO_Aspect contains NoData), *then* return the LandUse cell value, *else* return a value of 100.

You used the IsNull function with the Confunction to replace the NoData value with the value 100.

Starting with step 22, you want to update once again the LandUse raster with the proposed forest sites using the Over operator. But first you have to assign the NoData cells a value. The first option is quite intuitive if you use the **Reclassify** tool.

The second option describes the steps when you use the Raster Calculator dialog:

IsNull("Reforestration")

The IsNull function tests the Reforestration raster cells for the NoData value and returns true (1). All other values from Reforestration will have the false value (0).

Con("ForestNoData"= =0,"Reforestation",0)

This means that if a cell from ForestNoData is equal to 0, then return the Reforestation cell value, else return a value of 0.

Con("Forest_Final"= =1,101,0)

This means that *if* a cell from <code>Forest_Final</code> is equal to 1, *then* return the 101 value, *else* return a value of 0. The Con function will return <code>NoData</code> when no value is given for the false argument.

You have used the IsNull function with the Confunction to replace the NoData value with the LandUse cell values.

Working with Cell Statistics

ArcGIS Spatial Analyst classifies the statistical functions in three basic groups: local, neighborhood, and zonal. In this recipe, you will work with the **Local Cell Statistics** tool. The Cell Statistics function compares the corresponding cells in two or more raster datasets and calculates descriptive statistics, such as: Majority, Mean, Median, or Standard Deviation.



For theoretical aspects about statistical methods, please refer to Statistical Methods For Geography, Peter Rogerson, SAGE Publications Ltd., Inc., 2001.



Getting ready

In the previous recipe, *Working with Map Algebra*, you have updated the LandUse raster dataset with new forest and fruit orchard sites. In this recipe, you will compare the LandUse raster created in 2010 with the LandUse 2015 raster created in 2015.

How to do it...

Follow these steps to learn how to work with the **Cell Statistics** tool:

- Start ArcMap and open the existing map document Statistics.mxd from <drive>:\PacktPublishing\Data\SpatialAnalyst\CellStatistics.
- 2. Open **ArcToolbox**. Go to **Geoprocessing** | **Environments** and set the geoprocessing environment as follows:
 - Workspace | Current Workspace: ... \SpatialAnalyst\ CellStatistics\TOPO.gdb and Scratch Workspace: ... \ SpatialAnalyst\CellStatistics\ScratchTOPO.gdb
 - Output Coordinates: Same as the LandUse layer
 - Raster Analysis | Cell Size: Same as the LandUse layer and Mask: LandUse
- 3. To find the logical difference between the LandUse and LandUse_2015 raster layers, you will use the Cell Statistics functions.
- 4. In ArcToolbox, expand Spatial Analyst Tools | Local, and double-click on the Cell Statistics tool. Set the following parameters:
 - □ Input raster or constant value 1: ScratchTOPO.gdb\LandUse
 - □ Input raster or constant value 2: ScratchTOPO.gdb\LandUse_2015
 - **Output raster**: ScratchTOPO.gdb\LandUse Diff
 - Overlay statistic (optional): VARIETY
 - Output raster: ScratchTOPO.gdb\LandUse Diff
 - Check Ignore NoData in calculation (optional)
- 5. Click on **OK**. The cells with **value 2** are representing areas that have changed. Turn off all raster layers except the LandUse_Diff layer.


Let's find the land use types that have been changed:

272

6. In **ArcToolbox**, expand **Spatial Analyst Tools** | **Conditional**, and double-click on the **Con** tool. Set the parameters as shown in the following screenshot:

🔨 Con	
Input conditional raster	Con
LandUse_Diff 🗾 🖻	
Expression (optional)	Performs a conditional
Value >1	if/else
Input true raster or constant value	evaluation on
LandUse 🗾 🖆	each of the
Input false raster or constant value (optional)	input cells of an input
0 💌 🖻	raster.
Output raster	
esktop\SpatialAnalyst\CellStatistics\Old_LandUse 🔂 🥃	
	~
OK Cancel Environments << Hide Help	Tool Help


7. Click on **OK**. Turn off the LandUse_Diff layer, and turn on **LandUse** and Old_LandUse. Inspect the results. Symbolize the layer: **Color Schema**: Terra Tones; double-click on the symbol of value 0 to set **NoColor**; and edit the **Label** column, as shown in the following screenshot:





Now, we want to know the new land use types:

- 8. Reopen the **Con** tool. Set the following:
 - Input conditional raster: ScratchTOPO.gdb\LandUse_Diff
 - Build the following expression: Value >1
 - □ Input raster or constant value 1: ScratchTOPO.gdb\LandUse 2015
 - □ Input false raster or constant value (optional): 0
 - Output raster: ScratchTOPO5000.gdb\New LandUse
- 9. Click on OK. Inspect the results. Turn off the Old_LandUse layer and turn on the New_LandUse layer. Inspect the results. Symbolize the layer as follows: Color Schema: Green Bright; double-click on the symbol of value 0 to set NoColor; and edit the Label column, as shown in the following screenshot:



10. Save your map and close ArcMap.

You can find the results at <drive>:\PacktPublishing\Data\SpatialAnalyst\ CellStatistics.

How it works...

Using the **Cell Statistics** tool is quite simple, but the output raster contains only two values, 1, which means no change in land use, and 2, which indicates land use change.

In the previous steps, you answered the following questions:

• Question 1: What are the old land use types that have been changed?

You built the following expression: *if* a cell from LandUse_Diff is greater than 1, *then* return the LandUse value, *else* return a value of 0.

Answer: Arable, Pasture, and Meadow land use.

• Question 2: What are the new land use types for the changed areas?

You built the following expression: *if* a cell from LandUse_Diff is greater than 1, *then* return the LandUse 2015 value, *else* return a value of 0.

Answer: Fruit orchard and Forest land use.

There's more...

There is a shortcut to obtain the old land use types that have been changed (Old LandUse results):

- 1. Start ArcMap and open the previous map document Statistics.mxd.
- 2. In **ArcToolbox**, expand **Spatial Analyst Tools** | **Math** | **Logical** and double-click on the **Diff** tool. Set the following parameters:
 - □ Input raster or constant value 1: ScratchTOPO5000.gdb\LandUse
 - Input raster or constant value 2: ScratchTOPO5000.gdb\LandUse_ Update
 - Output raster: ScratchTOPO5000.gdb\Difference
- 3. Click on **OK**. Save your map and close ArcMap.

You have obtained the *old land use* for those areas planned for plantation. The cells with value 0 represent the cells that have the same values in both rasters. Be aware of the order of the input raster because the first raster cell values will be returned if the cell values are different in the first raster and the second raster.



Generalizing a raster

In the raster dataset, a **zone** is a class of elements represented by one or more cells that are connected or disconnected and that have the same value. The LandUse layer has zones or types of parcels, such as Arable, Pasture, Forest, and so on.

The Arable zone with the cell value 11 has a lot of disconnected areas or regions. A **region** is a group of connected cells having the same value. A zone is composed of one or more regions.

Getting ready

In this recipe, you will generalize the LandUse_2015 raster. The generalization process will change the values of the small-region areas to the values of the larger neighbor regions. The parcels with area below 625 meters square are not represented in a classic topographic map at scale 1:5,000. On the sheet map, this polygon area means a square of 5 millimeters. The LandUse_2015 raster has a cell size of 0.5 meters. For this reason, you will dissolve the regions smaller than $50 \times 50 = 2500$ cells.

The roads, rivers, and build-up areas should not be affected by the generalization process (for example, edge changed or dissolved). Surface types such as arable, pasture, and vineyard will be affected by generalization. Here's how the resultant map looks:



-276

How to do it...

Follow these steps to generalize the LandUse 2015 raster:

- Start ArcMap and open an existing map document Generalised.mxd from <drive>:\PacktPublishing\Data\SpatialAnalyst\Generalised.
- 2. Open the **ArcToolbox**. Go to **Geoprocessing** | **Environments** and set the geoprocessing environment, as follows:
 - Workspace | Current Workspace: Data\SpatialAnalyst\ Generalised\TOPO.gdb and Scratch Workspace: Data\ SpatialAnalyst\Generalised\ScratchTOPO.gdb
 - Output Coordinates: Same as the LandUse 2015 layer
 - Raster Analysis | Cell Size: Same as the LandUse_2015 layer and Mask: <none>

In the next step, you will exclude from spatial analysis the following zones: Hydrography, Transportation, and Other Terrains (for example, built-up area):

- 3. In **ArcToolbox**, go to **Spatial Analyst Tools** | **Conditional**, and double-click on the **Con** tool. Set the following parameters:
 - Input conditional raster: LandUse_2015
 - Expression: Click on the SQL button and select Load to add Exclude.exp from the Generalised folder
 - Input true raster or constant value: LandUse 2015
 - Input false raster or constant value (optional): <none>
 - Output raster: ScratchTOPO.gdb\Con LandUse
- 4. Click on **OK**. In **ArcToolbox**, go to **Spatial Analyst Tools** | **Generalization**, and double-click on the **Region Group** tool. Set the following parameters:
 - Input raster: Con_LandUse
 - **Output raster:** ScratchTOPO.gdb\Regions
- Accept the default values for all other parameters. Click on OK. In ArcToolbox, go to Spatial Analyst Tools | Zonal, and double-click on the Zonal Geometry tool. Set the following parameters:
 - Input raster or feature zone data: Regions
 - D Zone field: Value
 - Output raster: ScratchTOPO.gdb\LandUse_Area



- **Geometry type (optional):** AREA
- **Output cell size (optional):** 0.5
- 6. Click on **OK**. In **ArcToolbox**, go to **Spatial Analyst Tools** | **Conditional**, and double-click on the **Set Null** tool.
- 7. You have two options: using LandUse_Area and area, or using Regions and number of cells. Set the following parameters:
 - □ Input conditional raster: LandUse Area, or type Regions
 - **Expression:** Value < 625 (second option: Count < 2500)
 - **Input false raster or constant value:** 1
 - Output raster: ScratchTOPO.gdb\BigArea
- 8. Click on **OK**. In **ArcToolbox**, go to **Spatial Analyst Tools** | **Generalization**, and double-click on the **Nibble** tool. Set the following parameters:
 - Input conditional raster: Con LandUse
 - Input raster mask: BigArea
 - **Output raster**: ScratchTOPO.gdb\Generalization
 - Uncheck Use NoData value if they are the nearest neighbor
- 9. Click on **OK**. In **ArcToolbox**, go to **Spatial Analyst Tools | Math | Logical**, and double-click on the **Is Null** tool. Set the following parameters:
 - Input raster: Generalization
 - Output raster: ScratchTOPO.gdb\LandUseNoData
- 10. Click on **OK**. In **ArcToolbox**, go to **Spatial Analyst Tools | Conditional**, and double-click on the **Con** tool. Set the following parameters:
 - Input conditional raster: LandUseNoData
 - **Expresion**: Value = 1
 - □ Input true raster or constant value: ScratchTOPO.gdb\LandUse 2015
 - Input false raster or constant value (optional): ScratchTOPO.gdb\ Generalization
 - Output raster: ScratchTOPO.gdb\GeneralisedLU
- 11. Click on **OK**. Symbolize the GeneralisedLU raster layer by importing LandUse_2015.lyr from the Generalised folder. Inspect the results with the **Pixel Inspector** tool.
- 12. Save your map and close ArcMap.

You can find the results at <drive>:\PacktPublishing\Data\SpatialAnalyst \ Generalised.



How it works...

This is how these steps work:

- ▶ At step 3, you excluded three zones by assigning them a NoData value.
- At step 4, you delimitated the regions for all land use zones. Every region from the Regions layer has a unique value and its associated zone value. In this way, you can identify the regions with a small number of cells.
- At step 5, you calculated the area of each zone from the raster.

In order to replace all regions smaller than 625 meters, you have to create two groups of regions: 1 = regions larger than 625 meters, and NoData = smaller region. When you use the Set Null function, you have two options: working with the area or the number of cells.

► At step 8, you used the Nibble clean-up function. You replaced the zone value from the Con_LandUse layer with the zone values of the nearest neighbor regions based on the raster mask built at step 7. The NoData cells from the mask raster indicate the cells that should change the zone value.

Your generalized raster does not contain the three zones excluded at step 3. At step 9, you assigned the true value 1 to NoData cells. At step 10, you updated the value 1 with the corresponding cell values from LandUse 2015.

There's more...

Let's work again with **Model Builder**. Open ArcCatalog and go to ...\SpatialAnalyst\ ModelBuilder. Expand **MyToolbox**, and open **Generalised a Thematic Raster** model in the **Edit** mode. Explore the model: it contains the entire workflow you already tested. Note that the output (derived raster) will be saved at ...\SpatialAnalyst\Generalised\TOPO_ Model.gdb. Running the entire model will take you around 15 minutes.

Creating density surfaces

Density surfaces estimate the concentrations of points or polylines per unit of area. ArcGIS allows you to create a density surface using two methods:

- Simple—calculate the cell values using a circular search area around the raster cell
- Kernel (Kernel Density Estimation or (KDE)—use a circular search area centered on the sample point or polyline feature; the cell value is calculated based on the overlapping kernel-density surface values



Getting ready

In this recipe, you will prepare data for analysis by representing the built-up area using the Buildings polygon feature class. You will use the **kernel** density function to estimate the number of buildings per square kilometer. Using the same function, you will create the density surfaces based on the selected features (for example, dwellings and dwellings made of clay) and based on an attribute field (for example, the number of families, population, and so on).

How to do it...

Follow these steps to create two density raster surfaces:

- Start ArcMap and open the existing map document DensitySurfaces.mxd from <drive>:\PacktPublishing\Data\SpatialAnalyst.
- 2. Open ArcToolbox and set the geoprocessing environment, as follows:
 - Workspace | Current Workspace: Data\SpatialAnalyst\ TOPO5000.gdb and Scratch Workspace: Data\SpatialAnalyst\ ScratchTOPO5000.gdb
 - Output Coordinates: Same as Input
 - **Cartography | Reference Scale**: 5000
 - **Raster Analysis | Cell Size:** 0.5

In the next step, you will delineate the built-up area that will define the density processing extent:

- 3. Open the Buildings attribute table. Notice the empty field named BuiltUp. You will use this field in the next step.
- 4. In **ArcToolbox**, go to **Cartography Tools** | **Generalization**, and double-click on the **Delineate Built-Up Areas** tool. Click on **Show Help** to see the meaning of every parameter. Set the following parameters:
 - □ Input Building Layers: TOPO5000.gdb\Buildings\Buildings
 - Identifier Field (optional): BuiltUp
 - Output Feature Class: TOPO5000.gdb\Boundaries\BuiltUp_Area
 - **Grouping Distance:** 1000 with unit as **Meters**
 - **Minimum Detail Size:** 5 with unit as **Meters**
 - **Edge Features (optional):** TOPO5000.gdb\Transportation\Road
 - Minimum Building Count (optional): 2
- 5. Click on **OK**. Notice that the BuiltUp field from the Buildings value attribute table has been populated with the building status code.



- Symbolize the BuiltUp_Area layer, as follows: Hollow style with Outline: Boundary, Township and Outline Width: 1.7. In the Table Of Contents section, move the layer below the Buildings and Road layers.
- 7. Let's create a point feature class from the Buildings polygon feature class. In **ArcToolbox**, go to **Data Management Tools** | **Features**, and double-click on the **Feature to Point** tool. Set the following parameters:
 - □ Input Feature: TOPO5000.gdb\Buildings\Buildings
 - Output Feature Class: TOPO5000.gdb\Buildings\BuildingsP
 - Check Inside (optional); click on OK
- Turn off all layers except BuildingsP and BuiltUp_Area. Go to Geoprocessing | Environments, and update the following parameter: Processing Extent: BuiltUp_Area.

Let's create a population density surface using a 200-meter search radius:

- 9. In **ArcToolbox**, go to **Spatial Analyst Tools** | **Density**, and double-click on the **Kernel Density** tool. Click on **Show Help** to see the meaning of every parameter. Set the following parameters:
 - Input Building Layers: BuildingsP
 - **Population field:** NumberPersons
 - **Output raster:** ScratchTOPO5000.gdb\Population 200
 - **Output cell size (optional):** 0.5
 - **Search radius (optional)**: 200
 - Area units (optional): SQUARE KILOMETERS; click on OK

Let's create a family's density surface using a 200-meter search radius:

- 10. In **ArcToolbox**, double-click on the **Kernel Density** tool. Set the following parameters:
 - Input Building Layers: BuildingsP
 - **D Population field:** NumberFamilies
 - Output raster: ScratchTOPO5000.gdb\Families 200
 - Set the rest of the parameters the same as at step 9; click on **OK**

Let's create a dwelling density surface using a 200-meters search radius:

11. Open the BuildingsP attribute table. Click on Table Options and select the Select By Attributes option. Build the following expression for the Use Of Buildings (CDC) field: CDC = 1. Click on Apply. The expression will select the Dwelling features. Based on the selected features, you will create a density surface.




12. In ArcToolbox, double-click on the Kernel Density tool. Set the following parameters:

- Input Building Layers: BuildingsP
- Population field: <none>
- **Output raster**: ScratchTOPO5000.gdb\Dwelling 200
- Set the rest of the parameters in the same way as in step 9; click on **OK**.

Let's do an empirical analysis based on the *old dwellings made of clay* and *population density*. We assume that elderly people have, in general, old dwellings. We expect the population density to be quite low in areas with a high density of clay houses.

13. Firstly, select the clay dwelling with the following expression: CMA = 4 AND CDC = 1. Secondly, repeat step 12, and create the OldDwellings_200 density surface based on the selected features. Explore the results by comparing the Population_200 and OldDwellings_200 density surfaces as shown in the following screenshot:



14. Save your map as MyDensitySurfaces.mxd and close ArcMap.

You can find the results at $<\texttt{drive}:\PacktPublishing\Data\SpatialAnalyst \ \Density.$



How it works...


From steps 4 to 8, you prepared your data for density analysis. For the density surface, we have used a constant value for the radius of the circular search area around the buildings. If you increase the value of the search radius, you will obtain a more generalized surface of density. This might help you to identify particular areas of density or hotspots that are not so obvious at a 200-meter radius.

Analyzing the least-cost path

A least-cost path analysis uses a cost-weighted distance surface and a cost-weighted direction surface to create the smallest cost of travelling path from the source to the destination. The cost refers to one or more factors that could affect the travel. Cost factors, such as slopes or speed-restriction areas, define the cost surfaces. Those cost surfaces can be combined if the cost values use a common scale (for example, from value 1—best to value 10—worst). A least-cost path will follow the cells with the smallest accumulated cost.

Getting ready

In the *Analyzing surfaces* recipe, you studied the visibility between two geodetic points in order to plan some topographic surveys. Let's suppose you have two teams for this topographic survey campaign. Now, it is time to plan the trip from your office to the field. Your best routes will follow the roads with shallow slopes. The following model shows the workflow of the next spatial analysis:





How to do it...

Follow these steps to create two least-cost paths:

- 2. Go to **Geoprocessing** | **Environments** and set the geoprocessing environment as follows:
 - Workspace | Current Workspace: Data\SpatialAnalyst\Least-CostPath\TOPO.gdb and Scratch Workspace: Data\SpatialAnalyst\ Least-CostPath \ScratchTOPO.gdb
 - Output Coordinates: Same as Input
 - **Processing Extent:** Same as the Trapezoid5000 layer
 - Raster | Analysis Cell Size: Same as the LandUse layer

In the next steps you will reclassify the cell values of the LandUse raster layer:

- 3. In **ArcToolbox**, expand **Spatial Analyst Tools** | **Reclass**, and double-click on the **Reclassify** tool to open the dialog box. Set the following parameters:
 - Input Raster: LandUse
 - Reclass field: Value
 - Reclassification: Modify the values of the New values column, as shown in the following table:

Old values	New values
11	3
12	4
13	5
14	6
15	7
21	8
31	10
41	1
42	9
51	2
NoData	NoData

- 4. Click on the **Save** button to save the values in the remap table (information table) named MyReclassLand. You can reuse this information table if you want to repeat the step. Continue to set the last two parameters:
 - Output Raster: ... ScratchTOPO.gdb\Reclass Land
 - Check Change missing values to NoData (optional)
- Click on OK. Symbolize the raster layer as follows: Color Schema to Red to Green. Click on the Symbols column to select Flip Colors. For Display NoData as, select Black. Click on OK. Open the Reclass_Land raster attribute table to inspect the result.

In the next steps, you will reclassify the cell values of the SlopePercent raster layer.

- 6. Open the **Reclassify** tool, and set the following parameters:
 - Input Raster: SlopePercent
 - Reclass field: Value
- 7. Click on the **Classify** button, and set the following parameters:

Classification		Classification Statistics	
Method: Manual	(1) -	Count:	23067708
Classes: 10 -		Minimum:	0
Data Exclusion		Maximum:	496.616211
		Sum:	78782664.031652
Exclusion	Sampling	Mean: Standard Deviation:	3.415279 14.484911
C <u>o</u> lumns: 100 🚔 [Show Std. Dev. Show Mean		Break Values
20000000구귀()- 15000000	(2) right click	496.616211	Break Values %
1000000-	Zoom In Reset Zoom		30 35 40 45
5000000	Center	2158 496.616211	ОК
Snap breaks to data values		395510 Elements in Class	Cancel



Old values	New values
0 - 2	1
2 - 5	2
5 - 7	3
7 - 15	4
15 - 25	5
25 - 30	6
30 - 35	7
35 - 40	8
40 - 45	9
45 - 496.616211	10
NoData	NoData

 Reclassification: Modify the values of the New values column, as shown in the following table:

- Output Raster: ... ScratchTOPO.gdb\Reclass_Slope
- Check Change missing values to NoData (optional)
- 8. Click on **OK**. Symbolize the raster layer as follows: **Color Schema** to Slope. For **Display NoData as** select Black. Click on **OK**. Open the Reclass_Slope raster attribute table to inspect the result.

In the next step, you will create a total-cost raster layer. You are expecting to obtain a total-cost raster layer with cell values from 2 to 20:

- 9. Expand **Spatial Analyst Tools** | **Math** and double-click on the **Plus** tool. Set the following parameters:
 - Input raster or constant value 1: Reclass Land
 - Input raster or constant value 2: Reclass Slope
 - **Output raster**: ScratchTOPO.gdb\TotalCost
- 10. Click on **OK**. Open the TotalCost raster attribute table to inspect the result.

Let's calculate the cost distance and cost direction starting from the ${\tt MyOffice}$ vector layer:


- 11. Expand **Spatial Analyst Tools** | **Distance** and double-click on the **Cost Distance** tool. Click on **Show Help** to see the meaning of every parameter. Set the following parameters:
 - Input raster or feature source data: MyOffice
 - Input cost raster: TotalCost

286

- Output distance raster: ScratchTOPO.gdb\DistancePoint
- Maximum distance (optional): <none>
- Output backlink raster (optional): ScratchTOPO.gdb\DirectionPoint
- 12. Click on **OK**. Running the **Cost Distance** tool will take you around 15 minutes.

Let's identify the least-cost path from the office to points 8 and 72:

- 13. Expand **Spatial Analyst Tools** | **Distance** and double-click on the **Cost Path tool**. Set the following parameters:
 - Input raster or feature destination data: TriangulationPoint
 - **Destination field (optional)**: TIP
 - Input cost distance raster: DistancePoint
 - Input cost backlink raster: DirectionPoint
 - **Output raster**: ScratchTOPO.gdb\LeastCostPath
 - □ Path type (optional): EACH CELL
- 14. Click on **OK**. You should obtain two least-cost paths, as shown in the following screenshot:



15. Inspect the results. Save your map as MyLeastCostPath.mxd and close ArcMap.


You can find the results at <drive>:\PacktPublishing\Data\SpatialAnalyst \ Least-CostPath\Results LeastCostPath.mxd.

How it works...

This is how these steps work:

- ► At step 3, you reclassified cell values for the LandUse raster layer. The new value 1 for code 41 means that Transportation is the best land use for our path. We will try to avoid crossing the Hydrography and Other Terrains (for example, built-up area) land use and value 10 indicates the worst choice.
- ► At step 6, you reclassified the cell values of the SlopePercent raster layer using the same scale values as the LandUse raster layer. The reclass value 1 corresponds to a shallow slope between 0 and 2 percent. This slope range is the most suitable for our path. Again, value 10 represents the worst slope range for the path.

With the two reclassified layers in a common scale, you created a total cost raster layer at step 9 using the **Plus** tool. At step 11, you calculated *the input for the least-cost path*: cost distance and the cost direction as shown in the following screenshots:



Cost distance values represent accumulated costs and not distance values. Cost direction values range between 1 and 8. The value 0 represents the source cell. The code from 1 to 8 represents the direction to the least-cost cell back to the source cell.

Going further, you calculated the least-cost path or the shortest path between the MyOffice source layer and the TriangulationPoint destination layer using the two cost surfaces. The least-cost paths follow the cells with the smallest distance and direction cost, and represent the smallest sum of cell cost between the source and two destinations.



There's more...

Open your previous map document MyLeastCostPath.mxd. In the **Catalog** window, go to Data\SpatialAnalyst\Least-CostPath\TOPO.gdb. Expand **MyToolbox** and open the **Least Cost Path** model in the **Edit** mode. Explore the model. Notice that the derived raster will be saved at ...SpatialAnalyst\Least-CostPath\TOPO.gdb. Running the entire model will take you around 20 minutes.

289—

In this chapter, we will cover the following topics:

- Creating 3D features from 2D features
- Creating a TIN surface
- Creating a terrain dataset
- Creating raster and TIN from a terrain dataset
- Intervisibility
- Creating a profile graph
- Creating an animation

Introduction

The **3D Analyst** extension allows you to display and analyze your 3D data. 3D data means 3D features, rasters, and **Triangulated Irregular Networks** (**TINs**). This 3D data contains a z-value. A z-value refers to an attribute other than the horizontal position (for example, projected *x* and *y* coordinates). In this chapter, your z-value will represent the normal heights (*gravity-related height*) expressed in meters.

The particular term **height** and the general term **elevation** are used interchangeably in this chapter because some ArcGIS instruments and parameters use the term: *elevation*. The term **elevation** means the height above a given level. In particular, our **height** term means the height above the local mean sea level.

According to the international standard ISO 19111:2007 on geographic information—spatial referencing by coordinates:

- A gravity-related height is a height dependent on Earth's gravity field.
- A normal height (H) is a gravity-related height that approximates the distance of a point above the mean sea level.
- A Mean Sea Level (MSL) is the average level of the surface of the sea over all stages of tide and seasonal variations. In the local context, MSL is calculated from observations at one or more points over a given period of time.



For theory about gravity-related height, please refer to Jonathan Iliffe and Roger Lott, Datums and Map Projections 2nd Edition; Whittles Publishing, 2012, pp.30-35 and pp. 135-140.

In this chapter, you will work in the ArcScene 3D environment.

Creating 3D features from 2D features

A 3D feature is a 2D feature that has elevation (height) values (z-values) stored in its geometry. When you are creating a new feature class in your geodatabase, you have from the first panel **Geometry Properties**: **Coordinate include Z values. Used to store 3D data**. In *Chapter 1, Designing Geodatabase,* you created feature classes that store only 2D features.

In this recipe, you will convert the existing simple features (2D) into 3D features using two methods:

- Based on the height values from a raster surface
- Based on the height values from the 2D feature's field attribute

Getting ready

In this recipe, you will work with the **ArcScene** desktop application. ArcScene documents are saved as . sxd files. Your scene document will contain:

- A raster surface layer created in Chapter 9, Working with Spatial Analyst, in the Analyzing surfaces recipe
- Two 2D feature classes: PointElevation and Buildings

292

How to do it...

Follow these steps to convert 2D features into 3D features:

- Start ArcScene and open an existing scene document 3DFeatures.sxd from <drive>:\PacktPublishing\Data\3DAnalyst.
- 2. From the **Geoprocessing** menu, select **Environments**. Set the geoprocessing environment as follows:
 - Workspace:
 Current Workspace: Data\3DAnalyst\TOPO5000.gdb
 Scratch Workspace: Data\3DAnalyst\ScratchTOPO5000.gdb
 - Output Coordinates: Same as Input
 - Processing Extent: Same as the Elevation layer

Let's set base heights for the layers and vertical exaggeration for the scene:


- In the Table Of Contents section, right-click on the Elevation raster layer, and navigate to Properties | Base Heights. Check Floating on a custom surface: Elevation. Click on Raster Resolution. For Base Surface, set Cellsize X to 2.5 and Cellsize Y to 2.5. Notice that the number of Rows and Columns is automatically updated. By decreasing the display resolution, you will improve the display performance. Click on OK.
- 2. Click on the **Rendering** tab, check **Render layer at all times**, and type 0.05 seconds for **Draw simpler level of detail if navigation refresh rate exceeds**.

The ArcScene redraws or renders the layers every time you make a navigation movement. By decreasing the refresh rate, ArcScene will only have time to draw a blue skeleton of your raster layer while you are exploring the scene with the **Navigate** tool. When you stop navigating the scene, the raster layer will render normally.

3. In the **Effects** section, choose 10 for the **Select the drawing priority** option. The **Elevation** layer will have the lowest drawing priority in comparison with other layers from the scene document. The highest priority is value 1. Click on **Apply** and **OK**.

293

4. Set the vertical exaggeration for the scene. From the View menu, navigate to Scene Properties | General. Select 2 for Vertical Exaggeration. Click on OK. Try to navigate around the scene using the Navigate tool, as shown in the following screenshot:



5. In ArcScene, 2D feature layers have their base height set to 0 by default. The PointElevation and Buildings 2D feature layers are displayed below the Elevation layer. Repeat step 3 for the PointElevation feature layer using the same surface base heights. For Select the drawing priority option, type 1. Set the base height for the Buildings feature layer and for the Select the drawing priority option, choose 5.

Your 2D feature layers have been added to the Elevation surface. Turn off the 2D feature layers. Let's convert the PointElevation 2D feature layers to a 3D feature layer:

- 6. In **ArcToolbox**, expand **3D Analyst Tools** | **3D Features**, and double-click on the **Feature to 3D by Attributes** tool. Click on **Show Help** to see the meaning of every parameter. Set the following parameters:
 - □ Input Features: TOPO5000.gdb\Relief\PointElevation
 - Output Feature Class: ScratchTOPO5000.gdb\ PointElevation3D
 - Height Field: Elevation
 - To Height Field (optional): <none>
- Click on OK. Notice that the PointElevation3D feature layer is directly displayed in the 3D space based on the z-value in the point geometry. Open its attribute table. The Shape field stores the Point Z geometry.

Let's convert the Building 2D polygon feature layers to a 3D feature layer using the Elevation surface raster, as follows:



- 8. In **ArcToolbox**, expand **3D Analyst Tools** | **Functional Surface**, and double-click on the **Interpolate Shape** tool. Click on **Show Help** to see the meaning of every parameter. Set the following parameters:
 - □ Input Surface: TOPO5000.gdb\Elevation
 - □ Input Feature Class: TOPO5000.gdb\Buildings\Buildings
 - Output Feature Class: ... \3DAnalyst\ScratchTOPO5000.gdb\ Buildings3D
 - Check Interpolate Vertices Only (optional)
- 9. Accept the default values for all other parameters. Click on OK.
- 10. Note that the Buildings3D feature layer is directly displayed in the 3D space based on the z-value into the polygon geometry. Open the attribute table of the Buildings3D feature. The **Shape** field stores the Polygon Z geometry.

Let's improve the 3D appearance of buildings by extruding the polygon features according to the number of levels, as follows:

- 11. In the **Table Of Contents** section, right-click on the Buildings3D layer, and navigate to **Properties** | **Extrusion**. Set the following parameters:
 - Check Extrude features in layer
 - Extrusion value or expression: [Stories] *3
 - Apply extrusion by: adding it to each feature's minimum height
- 12. Click on **OK** and explore the results, as shown in the following screenshot:

	•		-	Ē				
Po	intElevation	3D			E	Buildings3D		
	OBJECTID	Shape *	Elevation	NAME		Shape *	Destination	Shape_Area
	1	Point Z	250.3	N_C		Polygon Z	Dwelling	72.691014
	2	Point Z	250.2	N_C		Polygon Z	Dwelling annex	54.286597
	3	Point Z	248.8	N_C		Polygon Z	Industrial and municipal	215.751969
	4	Point Z	247.8	N_C		Polygon Z	Industrial and municipal	232.864066
			1	-				

13. Save your scene document as My3DFeatures.sxd and close ArcScene.

You can find the final results at <drive>:\PacktPublishing\ Data\3DAnalyst\3DFeatures.




How it works...

At step 6, you assigned z-values to point features directly from the **Elevation** field. The z from the **Shape** geometry field confirms the 3D feature type.

At step 8, the raster cell values were interpolated to the assigned z-values to every vertex of the 3D polygon feature.

For the PointElevation3D and Buildings3D layers, it's not necessary anymore to set the base heights (topographic surface). Note also that subtypes and domains were kept in the new 3D feature classes.

At step 11, you raised the building from the ground using the number of levels multiplied by 3. The value 3 could represent the height of one level expressed in meters. From the **Tools** toolbar, use **Measure tool** | **Measure Height** to measure the reservoir height above the topographic surface, as shown in the following screenshot:



See also

 To create a 3D surface using 2D features, please refer to the Creating a TIN surface recipe

296

Creating a TIN surface

A **Triangulated Irregular Network** (**TIN**) is mesh of non-overlapping triangles that represent a continuous surface. This surface is built by triangulating a set of points that have z-values using the **Delaunay triangulation** method. This method generates triangles that are as near as possible to an equilateral triangle. The set of points represent the primary source of height values (mass points) and incorporates point features or vertices of the polyline and polygon features.



For theoretical aspects about TIN and Delaunay triangulation, please refer to David O'Sullivan and David Unwin, Geographic Information Analysis, John Wiley & Sons, Inc., 2003, page 28 and 215 to 220.

Getting ready

In this recipe, you will create a TIN surface using 2D feature classes. You will also update the TIN surface with new, upcoming features, such as building footprints and a fish pond.

How to do it...

Follow these steps to create a TIN surface using the ArcScene environment:

 Start ArcScene and open an existing scene document TIN.sxd from <drive>:\ PacktPublishing\Data\3DAnalyst.

Keep the geoprocessing environment from the previous recipe. From the **Geoprocessing** menu, select **Geoprocessing Options**. Check whether **Background Processing** | **Enable** is unchecked to ensure that your process will run in the foreground. By selecting this option, you will not allow other work until the tool stops running.



- 2. In ArcToolbox, expand 3D Analyst Tools | Data Management | TIN, and double-click on the Create TIN tool. Set the following parameters:
 - Output TIN: 3DAnalyst\TIN\TOPO5k.gdb
 - Coordinate System: Pulkovo_1942_Adj_58_Stereo_70
 - Input Feature Class as shown in the following screenshot:

4			
Road	<none></none>	Hard_Line	<none></none>
WatercourseL	<none></none>	Hard_Line	<none></none>
ReliefElements	Elevation_1	Hard_Line	<none></none>
ContourLine	Elevation	Mass_Points	<none></none>
PointElevation	Elevation	Mass_Points	<none></none>
Input Features	Height Field	SF Type	Tag Field

In the next step, you will create a 3D feature class from the 2D feature class Buildings using this time Topo5k TIN as the height (elevation) source surface:

- 3. In **ArcToolbox**, expand **3D Analyst Tools** | **Functional Surface**, and double-click on the **Interpolate Shape** tool. Set the following parameters:
 - Input Surface: TOPO5k
 - □ Input Feature Class: TOPO5000.gdb\Buildings\Buildings
 - Output Feature Class: ScratchTOPO5000.gdb\Buildings3DFromTIN
 - Method (optional): LINEAR
 - Check Interpolate Vertices Only (optional)
- 4. Click on **OK**. In the **Table Of Contents** section, move the BuildingsFromTIN layer above all layers.


Let's update the TIN with buildings from the BuildingsFromTIN layer and with a fish pond from the Lake layer.

- 5. In ArcToolbox, expand 3D Analyst Tools | Data Management | TIN, and double-click on the Edit TIN tool. Set the following parameters:
 - Input TIN: 3DAnalyst\TIN\TOP05k.gdb
 - Input Feature Class as shown in the following screenshot:

Input Features	Height Field	Tag Field	SF Type	Use Z
Buildings3DFromTIN	Shape	<none></none>	Hard_Replace	true
Lake	Elevation	<none></none>	Hard_Replace	false

298

- 6. Uncheck Constrained Delaunay (optional) and click on OK.
- 7. In the Table Of Contents section, turn off all layers except Topo5k TIN, BuildingsFromTIN, and Lake. For the Lake feature layer, set Topo5k TIN as the base height, and for Layer offset, type 0.5. For the BuildingsFromTIN feature layer, set Extrusion | Extrusion value or expression to [Stories]*2. For the Topo5k TIN, go to Layer Properties | Symbology, and uncheck Edge types, and for Elevation, choose the Surface color ramp.
- 8. From **View | Scene Properties | General**, set **Vertical Exaggeration** to 2. You should obtain the following results:



- 9. Inspect the results. Using the **Identify** tool, click on the fishpond from the BuildingsFromTIN layer to get the following information. Aspect with values -1 means a flat area.
- 10. Save your scene document as MyTIN.sxd, and close ArcScene.

You can find the results at <drive>:\PacktPublishing\Data\3DAnalyst\TIN.

299

How it works...

The elevation (height) points and vertices of the contour lines will be used as mass points to define the TIN surface. You have used scarps, water courses, and roads as hard lines; therefore, the TIN triangles will not cross the linear features. Leave unchecked the **Constrained Delaunay (optional)** option; you will allow the Delaunay triangulation process to build multiple triangle edges on the hard lines (breaklines).

At step 5, you updated the TIN surface with flat areas with constant height values. The fishpond from the Lake 2D feature layer has the value 225 meters stored in the **Elevation** field. The building footprints from the BuildingsFromTIN 3D feature layer have z-values incorporated into the polygon geometry or the **Shape** field.

Creating a terrain dataset

A terrain is a multi-resolution surface stored as a feature class in a feature dataset within a geodatabase. A terrain does not actually store the represented surface unlike TINs or rasters, which do. A terrain only references the participating feature classes and derives TINs at various resolutions on the fly, depending on the display scale. A terrain must be created within a feature dataset together with the feature classes that are used in it. That way, the **terrain**, **terrain surface**, and **terrain dataset** terms are often used interchangeably. You cannot see a terrain surface in the ArcScene environment, but you can use the ArcMap and ArcGlobe applications.

The terrain is used for large amounts of data. In this recipe, you will work with **Light Detection and Ranging** (**LiDAR**) data. LiDAR is an optical remote-sensing technology that provides detailed 3D elevation data.



For further research about LiDAR remote-sensing technology, please refer to George Vosselman and Hand-Gerd Maas, Airborne and Terrestrial Laser Scanning, Whittles Publishing, 2010.

Getting ready

In this recipe, you will create a terrain using an ASCII text file that stores LiDAR point-cloud data. Your point cloud contains 5 million points. Those points represent a **Digital Terrain Model** (**DTM**) or ground data.

In Windows Explorer, go to the <drive>:\PacktPublishing\Data\3DAnalyst\LiDAR folder. Explore the dtm.xyz ASCII file with the Notepad application.



How to do it...

Follow these steps to create a terrain dataset:

- Start ArcCatalog and go to Customize | Extensions to check the 3D Analyst extension. In Catalog Tree, go to <drive>:\PacktPublishing\ Data\3DAnalyst\TOP05000.gdb.
- 2. Your geodatabase already contains an empty feature dataset named Terrain. Right-click on the Terrain feature dataset and choose Properties | XY Coordinate System. The current projected coordinate reference system is Pulkovo_1942_ Adj_58_Stereo_70 with the EPSG code as 3844. Click on Z Coordinate System. The vertical coordinate reference system is a national gravity-related height system called Constanta (Black Sea 1975) with the EPSG code as 5781.

In the next steps, you will calculate the basic statistics of dtm.xyz, and convert mass points from the ASCII file to a multipoint feature class:

- 3. In **ArcToolbox**, expand **3D Analyst Tools** | **Conversion** | **From File**, and double-click on the **Point File Information** tool. Set the following parameters:
 - Define the provided and the provided and
 - Output Feature Class: ... \3DAnalyst\TOPO5000.gdb\Terrain\ DTMInfo
 - □ File Format: XYZ
 - File Suffix: xyz:

Coordinate System (optional) | XY Coordinate System: National Grids | Europe: Pulkovo_1942_Adj_58_Stereo_70

Z Coordinate System: Europe: Constanta

- 4. Accept the default values for all other parameters. Click on **OK**. You have obtained a polygon feature that defines the XY extent of your LiDAR data.
- 5. Open ArcMap. Add the DTMInfo feature class to your map. Save your map document as MyTerrain.mxd in the ...Data\3DAnalyst folder. Open the DTMInfo attribute table to view the following statistical information: Pt_Count: 5,722,782 points; Pt_Spacing: 1.005; Z_Min: 214.77, and Z_Max: 250.85. Close the table and turn off the DTMInfo layer.
- 6. In ArcToolbox, expand 3D Analyst Tools | Conversion | From File, and double-click on the ASCII 3D to Feature Class tool. Set the following parameters:
 - Define the point Data Browse for Files: ... \3DAnalyst\LiDAR\dtm.xyz
 - □ File Format: XYZ
 - Output Feature Class: ... \3DAnalyst\TOPO5000.gdb\Terrain\ MassPoints



- Output Feature Class Type: MULTIPOINT
- Coordinate System (optional) | XY Coordinate System: National Grids | Europe | Pulkovo_1942_Adj_58_Stereo_70

Z Coordinate System: Europe | Constanta

- Average Point Spacing (optional): 1.005
- **•** File Suffix (optional): xyz
- 7. Accept the default values for all other parameters. Click on **OK**. Use the **Zoom In** or the **Magnifier** tool to look closely at the points, as shown in the following screenshot:

	Table Of Content	s 🗆 ×											
		=		Mag	gnifie	er							
	□ 🖉 MassP	oints E		•	Θ,	s.	٩	ж ЯК •	5 A 2 M			800% •	·
		nfo 💂		•	٠	٠	٠	•	•	•	٠	٠	•
Table	2		⊐×	•	:	•	:	•	•		•	•	•
E •	・ 電・ 囁 🎦 Points	M 🐔 🗙	×	•	•	•	•	٠	•	٠	٠	٠	•
	1 Multipoint Z	PointCount 5000		•	•	•	•	•	•	•	•	•	•
E	2 Multipoint Z 3 Multipoint Z	5000 5000	-	Ŀ	•	•	•	•	•	•	•	•	•
H	 ▲ 1249 		■										
SE 1	ut of 1249 Selected sPoints))											

Let's create the terrain surface:


- 8. In the **Catalog** window, right-click on the TOPO5000.gdb\Terrain feature dataset and navigate to **New | Terrain**. Set the following parameters:
 - **Enter a name for your terrain**: DTM
 - Check MassPoints and DTMInfo
 - Approximate point spacing: 1.005

-302-

- 9. Click on **Next**. Click on **Advanced**. Set the **Embedded** option to **Yes**. Notice the terrain fields. Click on **Next** and set the following parameters:
 - D Point selection method: Z Mean
 - Secondary thinning method: Moderate
 - **Secondary thinning threshold:** 0.5
- 10. Click on **Next.** Click on **Calculate Pyramid Properties**. **Adjust Terrain Pyramid Levels**, as shown in the following screenshot:

No.	Window Size Maximum Scale		
1	1	1000	
2	5	2500	
3	10	5000	
4	20	10000	

11. Click on **Next**. Inspect the parameter's summary. Click on **Finish**. Click on **Yes** to build the terrain. Add the DTM terrain to your map. Let's explore the terrain at different scales. Add the Lake feature class in your map document and **Zoom In** to the fishpond. Turn off the Lake layer to see the terrain surface. Display and explore the area of interest at different scales, as shown in the following screenshots:






- 12. Let's examine the properties of the DTM terrain layer. Right-click on the DTM layer and choose **Properties** | **Display**. Let's reduce the default number of points used in the rendering process. From the **Apply point limit** value, erase a zero to obtain the point 80,000. If you want to see the height when you point to the map, check **Show Map Tips**. Click on **OK**. Display and explore the area of interest at the scale 5,000 and 2,500. Apparently, there is no difference. But how about a 1:1,000 scale?
- 13. Let's display the contour lines for the DTM terrain. Right-click on the DTM layer and choose Properties | Symbology. In the Show section, click on the Add button, and select Contour with the same symbol. Click on Add and Dismiss. Click on the Import button to import the symbol and parameter values from ...\3D Analyst\Terrain\DTM.lyr. You should obtain the following results:

Layer Properties	a second of the second	×
General Source Displa	ay Symbology Fields Analysis	
Show:	Contour with the same symbol	Import
Edge types	Contour symbol	
	Minimum visible resolution: Overview -	
Add	Reference contour <u>h</u> eight: 100.0	
R <u>e</u> move	Contour interval: 2.5	
	Index contour <u>factor</u> : 5	
	OK Cancel	Apply

-304

14. Click on **OK**. Inspect the results. If you add the ContourLine 2D feature class, you can explore the difference between the topographic map surface at the scale 1:5,000 and a new terrain surface, as shown in the following screenshot:



15. In the **Table Of Contents** section, note that the **Window Size** label values is updated when you change the display scale. Save your map and close ArcMap.

You can find the results at ...\3DAnalyst\Terrain\Terrain.mxd.

How it works...

Before starting to load your LiDAR data into your geodatabase, you evaluated the point density. Because your ACSII file contains around five million records, you grouped the LiDAR points into *multipoint* features. The multipoint geometry reduces the size of the MassPoints output feature class and the number of rows in the attribute table.

The **Window Size** pyramid will divide the data extent into equal windows and will select the representative points with z Mean (a z-value closest to the mean). You choose this option because you want to avoid the extreme values. The resultant surface will be integrated in our product, which is a topographic map at the scale 1:5,000.

305

From steps 9 to 10, you defined the rules for display terrain (scalability). The **Moderate** secondary thinning method will eliminate irrelevant points but will preserve the linear discontinuities from your surface. If z-values in the window area are within 0.5 meters, then it will be considered a flat area and will result in a more generalized surface. The 0.5 meters represents twice the vertical accuracy of the LiDAR dataset. We assume that the vendor mentioned a vertical accuracy of 25 centimeters.

At step 10, you defined four pyramid levels. Those levels define the vertical accuracy of the terrain, through four ranges of scales. Note that **Level 1** of **Terrain Pyramid** has a **Window Size** of 1 meter, which means that the full surface resolution will be displayed up to scale 1:1,000.

Creating raster and TIN from a terrain dataset

A terrain dataset can be converted to rasters or TINs using the geoprocessing tools from the **3D Analyst** toolbar. Why would we need to convert terrain to raster or TIN?

- Starting from large-scale source data, you might want to obtain derivative vector or raster surfaces for small-scale (for example 1:25,000) applications.
- You might need a raster surface to use statistical analysis tools from the Spatial Analyst extension.
- You might want to refine and update the surface with new polygon or polyline features having a precision corresponding to the 1:3,000 scale. You will need a TIN with a vertical accuracy corresponding to that scale.
- ▶ You might want to visualize your surfaces in ArcScene.
- > You might want to store the raster and TIN directly onto disk.

Getting ready

In this recipe, you will generate a raster and a TIN based on the DTM terrain surface created in the previous recipe.

You can start from your map document MyTerrain.mxd and skip step 1. Otherwise, you will use the terrain surface from ...\Data\3DAnalyst\Terrain\TOPO5000.gdb.



How to do it...

Follow these steps to convert a terrain dataset to raster and TIN using ArcMap:

- 1. Start ArcMap and open an existing map document, Terrain_ToRasterTIN.mxd, from ...\3DAnalyst\Terrain.
- 2. For the geoprocessing environment, set **Current Workspace** and **Scratch Workspace**: TOPO5000.gdb\Terrain. For **Processing Extent**, choose **Union of Inputs**.
- 3. In **ArcToolbox**, expand **3D Analyst Tools** | **Conversion** | **From Terrain**, and double-click on the **Terrain to Raster** tool. Set the parameters, as shown in the following screenshot:

🔨 Terrain to Raster	
Input Terrain DTM	^
Output Raster \3D Analyst\TerrainDTM_Raster.tif	
Output Data Type (optional) FLOAT	
Method (optional) NATURAL_NEIGHBORS	
Sampling Distance (optional) CELLSIZE 1	
Pyramid Level Resolution (optional)	÷
OK Cancel Environments Show Help >>	



4. Click on **OK**. In the **Table Of Contents** section, drag the DTM_Raster.tif surface above the DTM terrain surface. Change the symbology from Black to White to Elevation#1 Color Ramp. In the **Effects** toolbar, select DTM_Raster.tif as the layer drawing. Inspect the result using the **Swipe** tool, as shown in the following screenshot:



5. In **ArcToolbox**, expand **3D Analyst Tools** | **Conversion** | **From Terrain**, and double-click on the **Terrain to TIN** tool. Set the parameters, as shown in the following screenshot:

🔨 Terrain to TIN	
Input Terrain	^
Output TIN\3D Analyst\Terrain\DTM_TIN	
Pyramid Level Resolution (optional)	
Maximum Number of Nodes (optional) 5000000	
☑ Clip to Extent (optional)	Ŧ
OK Cancel Environments Show Help >>	



- 6. Click on **OK**. In the **Table Of Contents** section, drag the DEM_TIN surface above the DTM raster surface. Inspect the result in the same manner as the step 4 screenshot.
- 7. Save your map as MyTerrain ToRasterTIN.mxd and close ArcMap.

You can find the final results at ...\Data\3DAnalyst\Terrain\ ResultsTerrain_ ToRasterTIN.mxd.

How it works...

At step 3, you converted the terrain surface to a raster surface in the TIFF format. You used the **natural neighbors** interpolation method to obtain a smoother raster surface. Notice that you have to mention the .tif file extension to create a raster in the TIFF format. To define the cell size of your output raster, you mentioned **CELLSIZE** as 1. You will not improve the accuracy having a cell size smaller than the average point spacing of your initial LiDAR data. You have kept the full resolution of the input terrain by accepting the value 0 for the **Pyramid Level Resolution** parameter.

At step 5, you converted the terrain surface to a TIN surface. If you keep the value 0 for **Pyramid Level Resolution**, your geoprocessing tool will fail and display the message, **The TIN will be too big**. This is because of the allowed number of mass points in a TIN—up to 5,000,000. You chose **Level 1** and accepted the default number of nodes.

Intervisibility

Intervisibility refers to the analysis of a *sight line* between an observer and a target feature *through potential obstructions* such as 3D surfaces or features.

Getting ready

We continue to plan the topographic survey campaign mentioned in *Chapter 9*, *Working with Spatial Analyst*, in the *Analyzing surfaces* and *Analyzing the least-cost path* recipes. In this recipe, you will analyze the visibility between three geodetic points and buildings (reservoirs and two churches).

TriangulationPoint3D has an attribute field named **SurveyInstruments** that stores the normal height (H) of the instrument calculated as the sum of the **Height Black Sea'75** field and a constant value of 1.5 meters (height of the survey instrument).


Buildings3D has a field named **H_Buildings** that stores the height calculated as the sum of the **Z_Mean**, the normal height (H) field, and the approximate height of the building. The **Z_Mean** field has been calculated using the **Add Z Informative** tool.

The Buildings3D feature and the Elevation surface will be used as potential obstructions.



How to do it...

Follow these steps to analyze the visibility between the 3D triangulation points and the polygon buildings, as shown in the following screenshot:



- 2. Firstly, you will select the reservoirs and two churches. Open the Buildings3D attribute table. Open the **Select By Attributes** tool and type the expression: CFC = 319 OR CFC = 27. Click on **Apply**.
- Only selected features will be used as target polygon features. In ArcToolbox, go to 3D Analyst Tools | Visibility, and double-click on the Construct Sight Lines tool. Set the following parameters:
 - **Observer Points:** TriangulationPoint3D
 - Target Features: Buildings3D



- Output: ... \Intervisibility \TOPO5000.gdb \SightLines
- Observer Height Field (optional): SurveyInstrument
- **Target Height Field (optional)**: H_Building
- Join Field (optional): <none>
- **Sampling Distance (optional)**: 100
- Check Output the Direction (optional)
- 4. Click on OK. Open the SightLines attribute table to inspect the fields. Based on those 33 sight lines, you will analyze the visibility. In ArcToolbox, go to 3D Analyst Tools | Visibility, and double-click on the Intervisibility tool. This tool will modify the input SightLines layer. Set the following parameters:
 - Sight Lines: SightLines
 - Obstructions: For this, add the Buildings3D and Elevation layers
- 5. Accept the default values for **Visible Field Name (optional)**. Click on **OK**. The SightLines attribute table has been updated with a new field: **VISIBLE**.

There are 7 sight lines with **VISIBLE** value 0, which means they are obstructed by the elevation surface or buildings. The remaining 26 sight lines with value 1 are not obstructed, and there is visibility between the observer and target features.

6. Save your scene as MyIntervisibility.sxd and close ArcScene.

You can find the final results at <drive>:\PacktPublishing\Data\3DAnalyst \ Intervisibility\Results Intervisibility.sxd.

How it works...

Please note that the result of the **Construct Sight Lines** tool is a 3D polyline layer. By setting the value 100 for **Sampling Distance (optional)**, we kept only one sight line between the triangulation points and the *first vertex* of every selected building feature, as shown in the previous image. If you type 0, a sight line will be created for every vertex of a building polygon.

Creating a profile graph

A profile graph shows the height changes along a given line. A profile graph can be created from:

- ▶ 3D line graphics (created with the **Steepest path** and **Line of Sight** tools)
- ► 3D polyline features (for example, geodatabase feature class and shapefile)



Working with 3D Analyst

Getting ready


In this recipe, you will learn how to generate a profile graph using:

- ▶ 3D polylines from the SightLines3D feature class
- Elevation raster as a topographic surface

To generate a profile graph, you have to use the ArcMap environment and the **3D Analyst** toolbar.

How to do it...

Follow these steps to generate profiles using the SightLines3D 3D polyline layers, as shown in the following screenshot:



-312

- 1. Start ArcMap and open an existing map document, Profile.mxd, from <drive>:\ PacktPublishing\Data\3DAnalyst\ElevationProfile.
- 2. Load the **3D Analyst** extension and add the 3D Analyst toolbar.
- 3. With the **Select Feature** tool, select a polyline feature from the SightLines3D layer. Click on the **Profile Graph** tool from the **3D Analyst** toolbar. The z-value is represented along the Y axis and distance is represented along the X axis.



If you select more polyline features, you will obtain more profiles in the same graph.

- Right-click on the profile graph, select the Properties option, and select the Appearance tab. For General graph properties, edit Title and Footer, and for Axis properties, add Title for Left and Bottom, as shown in the preceding screenshot. Click on OK.
- 5. Right-click on the profile graph, and select the **Save** option to save your graph as the MyProfile_P73ToReservoir.grf graph file to the ...\3DAnalyst\ ElevationProfile folder.
- 6. Right-click on the profile graph and select the **Export** option. In the **Picture** frame, select the **as PDF** format and accept the default parameters. Click on **Save** and go to the previous location. Save the PDF file as MyElevationProfile.pdf.
- Select the Data tab, check Excel Format, and accept the default parameters. Click on Save and repeat the previous step. Inspect the results with the Windows Explorer application.
- 8. In ArcMap, close the graph window. Go to **View** | **Graphs** and select **Manage Graphs**. If you right-click on ResultsProfile_P73ToReservoir, you will find the same options from steps 5 and 6. To reopen your graph, double-click on the selected graph. Explore by yourself **Advanced Properties**.
- 9. Save your map document as MyProfile.mxd and close ArcMap.

You can find the final results at <drive>:\PacktPublishing\Data\3DAnalyst\ ElevationProfile\ResultsProfile.mxd. In the ResultsProfile.mxd map document, please go to **View | Graphs**, and explore all five profile graphs.

Working with 3D Analyst

How it works...


If you want to use the sight lines features created in the *Intervisibility* recipe, you have to go through the following steps:

- 1. Recreate the SightLines layer using the **Construct Sight Lines** tool, with **Observer Height Field (optional)** with the value Shape. Z and **Target Height Field (optional)** with the value Shape. Z. You will have a sight line at surface level. Notice that your sight lines have only two vertices along the polyline feature. Only two vertices are not enough for a profile graph.
- 2. Use the **Densify** tool with a **DISTANCE** of 50—unit as **Meters**—to add more vertices to the polyline features.
- 3. Use the **Interpolate Shape** tool with **Interpolate Vertices Only** checked. Your new vertices will have interpolated Z-values based on the Elevation surface.

The Profile_P73ToReservoir graph reflects the direction of polyline features. To change the direction of your path graphic (from point 73 to the reservoir), please follow the next steps: start an edit session, select the polyline with the **Edit Vertices** tool, right-click on the selected feature to change the polyline direction with **Flip**, and stop the edit session. Select the polyline and generate a new profile graph. Note that the direction of the graphic path has been changed.

There's more...

You can create profiles from a terrain surface, as shown in the following screenshot:





Open your map document MyProfile.mxd. Add the DTM terrain surface from ... 3DAnalyst\ ElevationProfile\TOPO5000.mdb\Terrain.

To activate the **Terrain Point Profile** tool, you have to symbolize the terrain surface with one of the three Terrain point renders. For the DTM terrain layer, choose the Terrain point elevation with graduated color ramp render.

In the **3D Analyst** toolbar, choose DTM as the surface layer, select the **Terrain Point Profile** tool, and click on two locations—the starting and ending points. Change the width for the black selection box, as shown in the preceding image. A new profile graph will be displayed. From **Properties** | **Appearance** of the profile graph, check the option **Graph in 3D view**.

Save and export your terrain point profile using the **View** | **Graphs** | **Manage Graphs** dialog box.

Creating an animation

There are two ways to create an animation:

- Capturing keyframes
- Recording your navigation through the scene

Keyframes are individual views. When you create an animation by capturing keyframes, you can use the **Capture View** tool or the **Animation Manager** dialog from the **Animation** toolbar. The rest of the views from the animation file will be interpolated based on those keyframes to result in a smooth animated picture.

Getting ready

In this recipe, you will create an animated tour of your 3D feature in ArcScene and export it to a video file. Before you start working, please watch the movies 3DFeatures_ByKeyFrames. avi and 3DFeatures_ByRecording.avi from the ...\Data\3DAnalyst\Animation folder. These are the two results you should obtain at the end of the exercise. You can use a media player such as **Windows Media Player** or **VLC**.

You can start with your scene document My3DFeatures.sxd from the Creating 3D features from 2D features recipe and skip step 1. Otherwise, use a scene document from the Animation folder.

Working with 3D Analyst


How to do it...

Follow these steps to create an ArcScene animation:

1. Start ArcScene and open an existing scene document 3DFeatures.sxd from ...\Data\3DAnalyst\Animation.

In the next steps, you will create an animation by capturing keyframes:

2. Firstly, you will load seven bookmarks that will help you in capturing camera keyframes. Go to **Bookmarks** | **Manage Bookmarks** and click on the **Load** button to add the KeyFrames_Animation.dat file from ...\3DAnalyst\Animation.You will load seven bookmarks, as shown in the following screenshot:



- 3. Close the **Bookmarks Manager** dialog. Explore all seven bookmarks and finish by choosing the first bookmark.
- 4. From **Customize** | **Toolbars**, add the **Animation** toolbar. From the **Animation** toolbar, select the **Animation** | **Animation Manager** | **Keyframes** tab. Move the **Animation Manager** dialog to the right-hand side of the scene.

Let's capture some keyframes for your animation.



5. From the **Animation Manager** dialog window, click on the **Create** button, and set the parameters as shown in the following screenshot:

Create Animation Keyframe	×
Ţype:	Camera 🔹
☑ Import from bookmark	KeyFrame 1
Source object:	Camera of Main Viewer 🔹
Destination track:	View capture track 👻
	New
Keyframe name:	¢amera keyframe 1
	Create Close

- 6. Check the **Import from bookmark** option and select the first bookmark named KeyFrame 1. Click on the **Create** button. Note that the **Animation Manager** dialog window has been updated with the Camera keyframe 1.
- 7. Repeat step 6 for the remaining bookmarks (from KeyFrame 2 to KeyFrame 7). You have to capture all seven keyframes of the animation, as shown in the following screenshot:

¥	Animation Manager									
	Keyframes Tracks Time View									
	Keyf	rames of 1	Type:	Camer	ra 🔻	In Track:	View capture	e track		
		Time	Name		Projection Type	Target:X	Target:Y	View		
	0 1	0.000 0.297	Camera keyfran Camera keyfran		Perspective Perspective	535845.923 535845.923	366990.35 366990.35	Update		
	2	0.381	Camera keyfrar	ne 3	Perspective	535798.541	367036.25	Create		
	3	0.501	Camera keyfrar	ne 4	Perspective	535696.780	367564.94			
	4	0.577	Camera keyfrar		Perspective	535696.780	367564.94	Properties		
	5	0.773 1.000	Camera keyfrar Camera keyfrar		Perspective Perspective	535696.780 535696.780	367564.94 367564.94	Remove		
	•		III				Þ	Remove <u>A</u> ll		
	Reset Times Distribute time stamps evenly Change temporal order:									
								Close		



Working with 3D Analyst

- 8. Close the **Create animation Keyframe** window. Explore all the columns of Keyframes. Select the **Time View** tab to see the capture track line of your animation. Leave open the **Animation Manager** dialog window.
- 9. From the **Animation** toolbar, select the **Open Animation Control** button, as shown in the following screenshots:




10. To adjust the default animation duration, click on the **Options** button, and change **Play Options** | **By duration** to 15 seconds. Accept default values for all other parameters. Click on the **Options** button again to collapse the dialog box. To watch the animation, click on the **Play** button.



To switch to the fullscreen view, press the *F11* key. To leave the fullscreen view, press the *F11* key again.

11. While you are watching your animation, notice the capture track line from the **Animation Manager** dialog window, as shown in the following screenshot:






12. Let's save the animation into an animation file with the .asa extension. From the Animation toolbar, select Save Animation File. Save your animation as MyKeyFrames.asa in ...Data\3DAnalyst\Animation. Select the Export Animation option to export your animation file to an AVI file MyKeyFrames.avi. In the Video Compression dialog window, accept the default Compressor as Microsoft Video 1, and click on OK.

In the next steps, you will create an animation by recording a flying through the scene:

- In the Animation Manager dialog window, select the Keyframes tab, and click on Remove All. From the Animation toolbar, select the Open Animation Control button. From the Bookmarks menu, select KeyFrame 2.
- 14. To start recording, perform the following steps:
 - Select the Fly tool from the Tools toolbar.
 - Click on the Record button from Open Animation Control to start recording.
 - Left-click to start navigating as a virtual airplane. Notice the speed values in the lower-left corner of the scene, as shown in the following screenshot:



To control the flight, press the Shift key to maintain a constant altitude, use the left-click to increase the speed and right-click to decrease the speed. A negative speed value (for example, -1, -2) means backwards flight.

- After 5-10 seconds, stop flying by pressing the Esc key or the mouse wheel.
- 15. Click on the **Record** button again to stop recording.
- 16. The **Animation Manager** | **Keyframes** dialog window has been updated with the corresponding keyframes when you have to stop recording. Check also the **Tracks** and **Time View** tabs. Watch your recorded navigation by pressing **Play** from **Animation Control**.



Working with 3D Analyst -

- 17. If you are not satisfied with the result, in **Animation Manager** | **Keyframes**, click on the **Remove All** button and start recording once again.
- 18. Repeat step 30 to save your animation as MyRecording.asa, and to export it as MyRecording.avi. Close the dialog windows and the ArcScene application.

Watch MyKeyFrames.avi and MyRecording.avi using a video player.

How it works...

In the **Animation Manager** | **Keyframes** dialog window, you can erase and replace any keyframe from your animation by selecting its ID and using the **Remove** button. Also, you can change the order of keyframes using the **Change temporal order** arrows.

At step 11, you can change the position or timing of every keyframe (small green square) along the capture-track red line. If your keyframes are too close, your animation will proceed rapidly. If your keyframes are too distant, your animation will move slowly. To improve the timing, click on the **Keyframes** tab, check **Distribute time stamps evenly**, and click on **Reset Times**. These steps will be reflected in the **Time View** window and will smoothen the animation.



In this chapter, we will cover the following topics:

- Exporting file geodatabase to different data formats
- Importing data from the XML format
- Importing vector data
- Importing raster data
- Spatial ETL

Introduction

Interoperability means the capability of two or more systems to exchange information and use/interpret the information shared without knowledge of the data structure. According to the online ESRI GIS Dictionary:

The interoperability is required for a GIS user using software from one vendor to study data compiled with GIS software from a different provider.

There are two important aspects of data interoperability in GIS:

- Spatial data type (for example, GIS, CAD, raster, XML, and LiDAR)
- ▶ Spatial data format (for example, shapefile, DWG, ECW, GML, and XYZ)

Data standards support you in dealing with data interoperability issues. Standards refer to formats, data models, or both.

Here you have some examples of international and national spatial standards:

- ISO/TC 211 Geographic information/Geomatics: http://www.iso.org
- Open Geospatial Consortium: http://www.opengeospatial.org
 Ordnance Survey MasterMap:

http://www.ordnancesurvey.co.uk

The **ArcGIS Data Interoperability** extension is a spatial **Extract/Transform/Load** (**ETL**) toolset that use the **Feature Manipulation Engine** (**FME**) technology from Safe Software Inc. Spatial ETL allows you to read (extract), transform, and write (load) over 70 spatial data formats.

For more details about data interoperability, please refer to:


- http://www.esri.com/products/technologytopics/standards
- Online ArcGIS Help (10.2) by navigating to Extensions | Data Interoperability at http://resources.arcgis.com/en/ help/main/10.2

Exporting file geodatabase to different data formats

In **ArcToolbox** | **Conversion Tools**, you will find a lot of tools to convert geodatabase data to another format. With the **Search** tool, you can find four tool types: **Script** (for example, Python file–.py), **Built-in**, **Model**, and **Specialized** (for example, **Spatial ETL Tool**). Use the **Search** window for a quick built-in tool search with the **Tools** filter and the **Local Search** index option, as shown in the following screenshots:

-322

Chapter 11



Getting ready

In this recipe, you will migrate a geodatabase into the **Extensible Markup Language** (**XML**) interchange format and the Esri shapefile format using the ArcCatalog context menu.

The XML workspace document stores the specification of the geodatabase and the data stored in it. It is a data exchange format used for:

- Sharing geodatabase data and schema to other applications
- > Adding more data, domains, objects, and rules to an existing geodatabase

You will exclude data and will export only the schema of an existing file geodatabase. In the second part of this exercise, you will transfer the subtype and domain descriptions as additional field attributes in the shapefile format.




How to do it...

Follow these steps to export a file geodatabase using ArcCatalog:

1. Start ArcCatalog click on the **Connect To Folder** tool from the **Standard** toolbar, and navigate to <drive>:\PacktPublishing\Data\Interoperability. Click on **OK**.

In the next steps, you will export the geodatabase schema to an XML file, as shown in the following screenshot:



- In Catalog Tree, go to Interoperability\SourceData, and expand TOPO5000. gdb to explore the contents. Right-click on TOPO5000.gdb and navigate to Export | XML Workspace Document.
- 3. You will export only the schema of the geodatabase without data. Check the **Schema Only** option.
- 4. For **Specify the output XML file**, navigate to ...\Data\Interoperability\ MyResults, and type TOPO5000. Click on **Save**. As you will not export data, uncheck the **Export Metadata** option. You will edit your own metadata information in the next recipe.

5. Click on **Next**. In the second panel, you can exclude one or more feature classes from the exported schema, as shown in the following screenshot:

Include	Data		Туре	· ·
	LandUse	LandUse	Feature Dataset	
1	LandUse	LandUse	Feature Class	
	Hydrography	Hydrography	Feature Dataset	-
1	WatercourseL	Watercourse	Feature Class	
1	WatercourseA	Watercourse	Feature Class	
1	Lake	Lake	Feature Class	
Include A	II Exclude All			4
mmary	Click to see a summary list	of the items you spec	ified.	

 After you have finished exploring all the listed feature classes, click on the **Include** All button to ensure that all data is checked. Click on **Finish**. You can now send the geodatabase schema by e-mail to your colleagues.

In the next steps, you will export the geodatabase data to the shapefile format:

7. Open the **Results** window to track the geo-processing tools. This will help you out in the next steps.



8. Your geodatabase has a lot of descriptions for subtypes and domains. Right-click on the TOPO5000.gdb\LandUse\LandUse feature class and navigate to **Export | To Shapefile (single)**. Set the parameters as shown in the following screenshot:

Feature Class to Feature Class	
Input Features	Feature Class to Feature Class
Output Location\Interoperability\MyResults\Shapefile	Converts a shapefile, coverage feature class, or
Output Feature Class LandUse.shp	geodatabase feature class to a shapefile or geodatabase
Expression (optional)	feature class.
Field Map (optional) CAT (Long) CAT (Text)	
- SHAPE_Leng (Double) - SHAPE_Area (Double) - SubCategor (Text)	-
OK Cancel Environments << Hide Help	Tool Help

- 9. Delete the SHAPE_Leng (Double), SHAPE_Area (Double), and SubCategor (Text) fields using the Delete button. Click on the Environments button, and go to the Fields parameter. Check Transfer field domain descriptions. This option will transfer to you the subtype and domain descriptions. You have worked with those descriptions in Chapter 1, Designing Geodatabase. Click on OK twice to run the tool.
- 10. In ArcCatalog, inspect the output shapefile in the **Preview**: **Table** mode view. Your shapefile now has the codes and descriptions for subtypes and domains.
- 11. Export the remaining feature classes at once by navigating to **Export** | **To Shapefile** (multiple).
- 12. From **Results** | **Current Session**, double-click on **Feature Class** to reopen the tool. Change only the **Input Features** parameter and **Output Feature Class**. The **Output Location** and the **Environment** parameter will remain unchanged. Click on **OK** to run the tool again. Explore the results.

How it works...

At step 4, even if you uncheck all feature classes from a feature dataset, the exported XML workspace document will keep the empty feature dataset. To see the XML file, you can use the Notepad++ free text editor.





For more details about the XML schema of your geodatabase, please refer to the Esri white paper, XML Schema of the Geodatabase.pdf.

At the feature class level, you can save the data into an XML file using **Export XML Recordset Document**.

When you are sharing your schema, it's good practice to document the XML workspace. You should keep the metadata information or create supplementary material (for example, a PDF containing summary information about the lineage of data, responsible party, coordinate reference system, and spatial resolution).

There's more...

In Chapter 10, Working with 3D Analyst, you worked with 3D features. If you want to see those buildings in the **Google Earth** application, you have to export the Buildings3D feature class to a **Keyhole Markup Language** (**KML**) format. For the next exercise, you need to install Google Earth for desktop from https://www.google.com/earth.



For more details about the KML format, please refer to:

- Online ArcGIS Help (10.2) navigating to Geodata | Data types | KML at http://resources.arcgis.com/ en/help/main/10.2
- Online Google documentation at http:// developers.google.com/kml

Follow these steps to import a feature class into Google Earth:

- 1. Start ArcCatalog. In **Catalog Tree**, go to ...\SourceData\TOPO5000.gdb. Firstly, prepare the Buildings3D feature class.
- 2. In **ArcToolbox**, expand **Data Management Tools** | **Projections and Transformation**, and double-click on the **Project** tool. Set the following parameters:
 - Input Dataset: SourceData\TOPO5000.gdb\Buildings\Buildings3D
 - Output Dataset: SourceData\TOPO5000.gdb\ Buildings3D_UTM35N
 - Output Coordinate System: Projected Coordinate Systems\UTM\
 WGS 1984\Northern Hemisphere\WGS 1984 UTM Zone 35N
 - Geographic Transformation (optional): Pulkovo_1942_Adj_1958_To_ WGS_1984_19



- 3. In ArcScene, add and symbolize Buildings3D_UTM35N. Extrude features in layers based on the [Stories] field.
- 4. In **ArcToolbox**, expand **Conversion Tools** | **To KML** and double-click on the Layer To KML tool. Set the following parameters:
 - □ Layer: Buildings3D UTM35N
 - Output File: MyResults\Buildings3D_UTM35N.kmz (the KMZ file format is a compressed KML)
 - Check Clamped feature to ground (optional). Click on OK.
- 5. Open the Google Earth application. Go to the **View** menu and check **Grid**. Go to **Tools** | **3D View** and check **Universal Transverse Mercator**. Click on **OK**.
- 6. Go to File | Open and browse to Buildings3D UTM35N.kmz. Explore the results.

You can find the results at <drive>:\PacktPublishing\Data\ Interoperability\ DataResults.

See also

 If you want to see how your colleagues will generate a geodatabase schema from the XML workspace document received from you, please go to the next recipe *Importing* data from the XML format


Importing data from the XML format

An XML file can transport and store geodatabase schema and spatial data. Geodatabase XML is Esri's XML-based interchange format used to share data (*workspace data*) and geodatabase schema in full or in part (*workspace definition*) between geodatabases or other software systems.

- 328

Getting ready

In this recipe, you will create a file geodatabase schema by importing an XML workspace document that contains only the workspace definition as shown in the following screenshot:



You will use the TOPO5000.XML file created in the previous exercise.

How to do <u>it...</u>

Follow these steps to create a file geodatabase using as a template an ArcGIS XML workspace document:

 In Catalog Tree, go to Interoperability\MyResults. Right-click on the MyResults folder and navigate to New | New File Geodatabase. Rename New File Geodatabase.gdb to MyTOPO.

2. Right-click on TOPO5000.gdb and navigate to **Import** | **XML Workspace Document**. Check **Schema Only** and specify the XML source to import by selecting the TOPO5000.XML file you created in the previous recipe. Click on **Next** and **Finish** to start importing schema as shown in the following screenshots:

Import XML Workspace Document	XML Import Workspace Schema
This wizard lets you import data and schema from an XML to geodatabase.	Importing XML Schema
Importing data to:\Interoperability\WyResults\WyTOPO.gdb	
What do you want to import:	\mathbf{U}
© <u>D</u> ata	
Schema Only	
Sgedfy the XML source to import: . \Interoperability/WyResults\TOPO5000.xml	Importing XML Schema: TriangulationPoint (0 Objects)
< Back Next > Cancel	Cancel

3. Expand MyTOPO.gdb to explore the contents.

You can find the results at <drive>:\PacktPublishing\Data\ Interoperability\ DataResults\MyTOPO_SchemaOnly.gdb.

How it works...

By importing an XML workspace document that stores a geodatabase schema, you saved a lot of time in defining the geodatabase structure. The feature datasets, feature classes, attribute domains, and subtypes are now built into the MyTOPO geodatabase.

There are lots of ArcGIS template data models at http://solutions.arcgis.com. Use your Esri global account created in *Chapter 7, Exporting Your Maps*, to download a sample data model from **ArcGIS for Local Government | Land Records | Aggregate Authoritative Data**.


There's more...

Let's add some metadata information to your geodatabase from an XML file:

1. In ArcCatalog, go to Customize | ArcCatalog Options, and select Metadata Style: ISO 19139 Metadata Implementation Specification. Click on OK.



 In Catalog Tree, go to Interoperability\MyResults, and select MyTOPO.gdb. Select the Description tab and click on Import. For Source Metadata, select MyTOPO_ISO19139.XML from the SourceData folder, as shown in the following screenshot:



3. Click on **OK**. Your metadata content has been updated with new information. Explore the contents.

While you are populating M_{Y} TOPO.gdb with data, it's good practice to create and update your metadata for every feature dataset and feature class from your geodatabase.

When you use ArcMap, you can view and edit metadata information from the **Catalog** context menu: right-click on the selected feature class and choose **Item Description**. Before starting to edit and export metadata elements, select the metadata style from the **Customize** | **ArcMap Options** | **Metadata** tab. The core metadata elements and the required elements and subelements might vary slightly depending on the metadata standard used (for example, ISO 19115, INSPIRE, FGDC CSDGM Metadata).



See also

► After you have built the structure of file geodatabase, you should populate it with the existing vector and raster datasets. To see the ArcGIS options, please explore the next recipes *Importing vector data* and *Importing raster data*.

Importing vector data

When you are importing existing vector data in your geodatabase, you have to inspect the following characteristics of your data:

- Source and data format (for example, internal/external, reliable, supported)
- > Spatial reference (for example, maybe you will need to transform or project the data)
- Attributes (for example, field data type: short integer, text, date)
- Corresponding scale of the source data
- Metadata information (for example, quality of data, access, use and legal constraints)

You have already added data to a file geodatabase:

- Using Load Data to add a feature class in the Editing features in a geodatabase recipe of Chapter 2, Editing Data
- Using Import from the ArcCatalog context menu to add a feature class in the Projecting vector data recipe of Chapter 3, Working with CRS
- Using Load Data and Export from the ArcCatalog context menu to add a DXF file from the external source in the Spatial joining features recipe of Chapter 4, Geoprocessing

Getting ready

In this recipe, you will convert a .csv and a .xlsx file to a new feature class. In addition, you will import an XML file and a shapefile data file in the MyTOPO geodatabase, as shown in the following screenshot:

□ 🚺 MyTOPO.gdb
🗆 🖶 LandUse
🖾 LandUse 🗕 🔤 🕱 LandUse.xml
🗆 🔁 Relief
😁 ContourLine 🛛 🖛 😁 ContourLine.shp
😁 ReliefElements 👘 👘 👘
SurveyPoints <a> survey_points_set1.csv
survey_points_set2.xlsx

All those four formats are stored in the \ldots \Interoperability\SourceData folder.



How to do it...

Follow these steps to convert the .csv and .xlsx file formats to a feature class:

- Start ArcMap and open an existing map document ImportData.mxd from <drive>:\PacktPublishing\Data\Interoperability\SourceData.
- 2. From the **File** menu, navigate to **Add Data** | **Add XY Data**. Set the following parameters:
 - Choose a table from the map or browse for another table: ... \ SourceData\survey_points_set1.csv
 - □ X Field: East (S42)
 - Y Field: North (S42)
 - D Z Field: Elevation (H)
 - Coordinate System of Input Coordinates: This parameter will inherit the coordinate system of the active data frame
- 3. Accept the default **Coordinate System** and click on **OK**. Read the warning message and click on **OK**.
- 4. Select the Add Data button and go to ...\SourceData. Double-click on survey_ points_set2.xlxs to see the Excel worksheet survey_points. Click on Add. To see a nonspatial table, select List By Source in the Table Of Contents section. Open the attribute table of the survey points worksheet to inspect the fields.
- 5. Right-click on the survey_points table and select **Display XY Data**. For **Specify the fields for the X, Y and Z coordinates**, set the following parameters:
 - X Field: East
 - Y Field: North
 - D Z Field: H
- 6. Accept the default **Coordinate System** and click on **OK**. Read the warning message and click on **OK**.

Let's export the point events to feature classes:

- Right-click on SurveyPoints_Set1.csv Events and select Data | Export Data. Set Output feature class: ... \Interoperability\MyResults\MyTOPO.gdb\ SurveyPoints_Set1. Click on OK.
- 8. Repeat step 7 for the survey_points Events layer and save it as SurveyPoints Set2. Inspect the attribute fields of both feature classes.



- 9. In **ArcToolbox**, expand **Data Management Tools** | **General**, and double-click on the **Merge** tool. Click on **Show Help** to see the meaning of every parameter. Set the following parameters:
 - □ Input Datasets: SurveyPoints Set1 and SurveyPoints Set2
 - **Output Feature Class**: MyTOPO.gdb\Relief\SurveyPoints
- 10. Accept all fields and click on **OK**. Open the attribute table of the SurveyPoints layer.
- 11. Notice that you have duplicated fields for the East, North, and H coordinates.

Before you start to use the **Merge** tool, you should check and rename the fields of your feature classes. Let's correct this:

- 12. Use **Select by Attribute** to select all features from set1 with **ID IS NULL**. Right-click on the **East** field, select **Field Calculator**, and double-click on the **[East_S42_]** field to build the following expression: East= [East S42]. Click on **OK**.
- 13. Repeat the previous step for the **North** and **H** fields. Erase the **East_S42**, **North** _**S42**, **Elevation_H**, and **ID** fields, as shown in the following screenshot:

Ta	Table 🗆 🗆 🗙									'×	
0											
Su	rveyPoints							-0-			×
	OBJECTID *	Shape *	East S42	North	S42	Elevation H	ID	East	North	н	
	92	Point Z	535588.643	31 36801	6.6623	227.2	<nel></nel>	535588.643	368016.6623	227.2	-
	93	Point Z	535672.06	83 36791	9.6451	225.8	<null></null>	535672.068	367919.6451	225.8	
	94	Point Z	535568.02	11 36788	37.3061	228	<null></null>	535568.021	367887.3061	228	
	95	Point Z	535165.423	39 3681.	6.6447	234	<null></null>	535165.423	368136.6447	234	
	96	Point Z	535313.05	85 36912	1.1781	236.4	<null></null>	535313.058	368121.1781	236.4	
	97	Point Z	535675.81	77 36809	3.0573	228.4	<null></null>	535675.817	368093.0573	228.4	
	98	Point Z	535794.862	29 36811	8.3661	229	<null></null>	535794.862	368118.3661	229	
	99	Point Z	535930.78	05 36802	26.9731	227.8	<nul></nul>	535930.780	368026.9731	227.8	
	100	Point Z	<null></null>	<null></null>		<null></null>	1	535999.676	368006.3511	227.78	
	101	Point Z	<null></null>	<null></null>		<null></null>	2	536030.140	368128.6771	243.8	
	102	Point 7	<nulls< td=""><td><nulls< td=""><td></td><td><nulls< td=""><td>3</td><td>535806 111</td><td>367947 7661</td><td>228.2</td><td>Ψ.</td></nulls<></td></nulls<></td></nulls<>	<nulls< td=""><td></td><td><nulls< td=""><td>3</td><td>535806 111</td><td>367947 7661</td><td>228.2</td><td>Ψ.</td></nulls<></td></nulls<>		<nulls< td=""><td>3</td><td>535806 111</td><td>367947 7661</td><td>228.2</td><td>Ψ.</td></nulls<>	3	535806 111	367947 7661	228.2	Ψ.
ŀ	I 0 ▶ I										
S	irveyPoints_S	et1 Surve	eyPoints_Set2	2 SurveyPo	ints						

14. Save your map document as MyImportData.mxd and close ArcMap.

In the next steps, you will continue to load a shapefile into the $M_{Y}TOPO$ geodatabase using the ArcCatalog context menu:



- 15. In **Catalog Tree**, go to your Interoperability folder connection, and expand the SourceData folder to explore the contents. If you inspect **Properties** | **Fields** of ContourLine.shp, you will notice that you don't have the information related to the types of contour lines. Inspect also the **Fields** of the ContourLine feature class. You have a subtype field called CNT that stores this information. You will load all polyline features into the Unknown Subtype, and later on, you can add more information.
- 16. Navigate to ... \MyResults\MyTOPO\Relief and right-click on the empty ContourLine feature class. Select Load | Load Data and set the following parameters from the panels:
 - Input data: ... \SourceData\ContourLine.shp
 - Click on Add
 - I want to load all features into a subtype: Unknown
 - For field mapping, accept Target and Matching Source Field: Elevation [double]
 - Check Load all of the source data
- 17. Click on **Finish**. In the **Preview** panel, inspect the geometry and attribute table.

In the next step, you will load data from an XML recordset document:

- 18. In **Catalog Tree**, navigate to MyTOPO\LandUse, and right-click on the empty LandUse feature class. Select **Load | Load XML Recordset Document** and set the following parameters from the panels:
 - Specify the XML source to load: LandUse.xml
 - Inspect and accept the fields for Target Field and Matching Source Field
- 19. Click on Finish. Inspect the result in the Preview panel.

You can find the results at ... \Interoperability \DataResults \MyTOPO.gdb.

How it works...

At steps 2 and 5, the survey points have been added in ArcMap as *event tables layers*. Those points are saved in map documents, but they are not permanent features. To save them, you exported them as a feature class in the MyTOPO.gdb geodatabase.

You can create a point feature class from the survey_points_set1.csv file using the ArcCatalog context menu. Right-click on the file and select **Create Feature Class | From XY Table**.

Before starting to load data from any format, it's important to evaluate the existing data. By carefully planning the load steps, you will avoid losing data in the field-mapping step, generating duplicate/residual data or failing the entire load process. Here, you have some supplementary steps:

- Change the data type of the attribute fields for the editable source data format (for example, shapefile, feature class)
- Export source data in an intermediary editable format (for example, from the DXF format to a file geodatabase feature class, or from an Excel table to a dBASE or file geodatabase table)
- Change the geometry of the source data according to the destination feature class

The field-mapping process can be a critical step if the data types of the target and source fields do not match properly.

Importing raster data

You can store one or more rasters in a geodatabase as:

- Individual raster datasets
- Mosaic dataset
- Raster catalog

You have already worked with the raster dataset in *Chapter 9*, *Working with Spatial Analyst* and *Chapter 10*, *Working with 3D Analyst*.

In this recipe, you will work with the mosaic dataset and the raster catalog.

A mosaic dataset creates a seamless view of two or more adjacent or non-adjacent images. In a mosaic dataset, all rasters have the same cell size, format, and coordinate system.

A raster catalog is a table that groups two or more raster datasets. In a catalog, rasters may have different cell sizes and different formats, but they must have the same coordinate system.

Getting ready

In this recipe, you will create a mosaic dataset using four rasters in the **Enhanced Compression Wavelet** (**ECW**) file format.



For more details about the ECW raster format, refer to http://www. hexagongeospatial.com/products/data-managementcompression/ecw.

All those four rasters are stored in the ... \Interoperability\SourceData\ECW folder.



How to do it...

Follow these steps to create a *raster catalog* and a *mosaic dataset* using the ArcCatalog context menu and the **ArcToolbox** tools:

- Start ArcCatalog. In the Catalog window, go to your Interoperability folder connection, and expand the SourceData\ECW folder to explore its contents. Those four rasters cover four small adjacent areas.
- 2. Right-click on the orthoimage_1.ecw raster, and select **Properties** | **General**. Inspect the properties of the raster, such as **Number of Bands**, **Pixel Depth**, and **Pyramids resampling**. Click on **OK** to close the dialog window.
- 3. From the **Geoprocessing** menu, select **Environments**. Set the geoprocessing environment as follows:
 - Workspace | Current and Scratch Workspace: ... \Interoperability \ MyResults \MyTopo.gdb
 - Output Coordinates | As Specified Below: Import from <Feature Dataset>
 - **Raster Storage | Pyramid levels:** 10
 - **Raster Storage | Compression**: LZ77; click on **OK**.

In the next step, you will learn how to manage your four rasters in a raster catalog:

- 4. In the MyResults folder, right-click on the MyTOPO geodatabase, and navigate to **New | Raster Catalog**. Set the following parameters:
 - **Output Location**: ... \MyResults\MyTopo.gdb
 - Raster Catalog Name: MyRasters
 - Raster Management Type (optional): MANAGED
- 5. Accept the default values for all other parameters. Click on OK.
- Let's load four ECW rasters. Right-click on the MyRasters raster catalog and navigate to Load | Load from Workspace. For Input Workspace, navigate to the ...\ SourceData\ECW folder. Leave the two remaining options unchecked. Click on OK.

7. Explore the raster catalog as shown in the following screenshot:



- 8. Use the **Expand Window** button **(1)** to open the raster catalog browser and the **Show Advanced Tools** button **(2)** to query a raster catalog.
- 9. The **Overview** panel displays the footprints of rasters, and the **Selection** panel displays the selected raster.

In the next step, you will learn to manage your four rasters in a raster mosaic:

- 10. Let's create first an empty container for rasters. In **Catalog Tree**, navigate to the MyResults folder, and right-click on the MyTOPO geodatabase. Navigate to **New** | **Mosaic Dataset** and set the following parameters:
 - Output Location: .. \MyResults\MyTopo.gdb
 - Mosaic Dataset Name: OrthophotoMap
 - Coordinate System: Import from MyTopo.gdb\LandUse
 - Product Definition (optional): NATURAL COLOR RGB
- 11. Accept the default values for all other parameters. Click on OK.
- 12. Let's add the rasters. In ArcToolbox, expand Data Management Tools | Raster | Mosaic Datasets, and double-click on the Add Rasters To Mosaic Dataset tool. Click on Show Help to see the meaning of every parameter. Set the following parameters:
 - □ Mosaic Dataset: MyTopo.gdb\OrthophotoMap
 - Raster Type: Raster Dataset
 - Input Data: Workspace

-338

- □ Navigate to ...\SourceData\ECW
- Check Updates Overviews
- 13. Accept the default values for all other parameters. Click on OK.
- 14. In ArcMap, open the MyImportData.mxd map document, and load your OrthophotoMap mosaic dataset, as shown in the following screenshots:




Table - Ortho	ophotoMap\Fo	otprint								
- B.	- I 🔂 🔂 🔟	御×								
Orthophotol	Map\Footprint				×	Orti	hophotoMa	ap\Bound	lary	
Raster	Name	CenterX*	CenterY *	Tag			OBJECTID	Shape	Shape Leng	Shape Area
<raste< td=""><td>orthoimage_1</td><td>535620.75</td><td>366390.5</td><td>Dataset</td><td></td><td></td><td>1</td><td>Polygon</td><td>7342</td><td>3166658.75</td></raste<>	orthoimage_1	535620.75	366390.5	Dataset			1	Polygon	7342	3166658.75
<raste< td=""><td>orthoimage_2</td><td>536343.25</td><td>366382</td><td>Dataset</td><td></td><td>F</td><td>- 20</td><td></td><td></td><td></td></raste<>	orthoimage_2	536343.25	366382	Dataset		F	- 20			
<raste< td=""><td>orthoimage_3</td><td>536325.25</td><td>367333</td><td>Dataset</td><td></td><td></td><td></td><td></td><td></td><td></td></raste<>	orthoimage_3	536325.25	367333	Dataset						
<raste< td=""><td>orthoimage_4</td><td>\$35692</td><td>367346.25</td><td>Dataset</td><td></td><td></td><td></td><td></td><td></td><td></td></raste<>	orthoimage_4	\$35692	367346.25	Dataset						
	m				٠	14		1 .	н 📄 🗖	
14 4	0 F H	0	out of 4 Select	ted)		(0	out of 1 Se	lected)		
Orthophoto	Map\Footprint					Ort	thophotoM	lap\Boun	dary	

- 15. Open and inspect the attribute table for the ${\tt Boundary}$ and ${\tt Footprint}$ layers.
- 16. Save your map and close ArcMap.



How it works...

At step 4, we chose **Raster Management Type (optional)** value as MANAGED. The raster catalog will be managed by the geodatabase. This means that your rasters will be stored in MyTopo.gdb. Each ECW raster will be stored as a separate raster dataset.

The UNMANAGED option will not convert the rasters, and the catalog will store only the path to the source rasters. You will not be able to see those rasters if the geodatabase or the referenced rasters are moved to another location.

A mosaic dataset will treat the four raster datasets as a single one. At step 12, the Footprint layer represents the extent of each individual raster from mosaic. The Boundary layer represents the edge of the combined rasters. If you want to change the display order of the rasters, right-click on the Image layer, and navigate to **Properties | Mosaic**.

Spatial ETL

In the previous recipes, you used the traditional data translation between two data types and formats. The ArcGIS Data Interoperability uses the FME functionality to extend the formats you can read, transform, and translate.

The **transformation** process allows you to manipulate the structure and content of your data. The transformation process occurs during the format translation process. **Translation** refers to the process of converting a data format into another data format using:

- Workspace: This is a container that stores the translation definition
- Reader and writer: These are the source and destination datasets
- Feature type: This is a feature class, layer, or object class
- **Feature**: This is the base component of the translation

You have three tools to translate and transform interoperability data:

- Quick Import: This imports any FME-supported format into a new geodatabase
- Quick Export: This exports any feature class and interoperability data to any FME-supported format
- Spatial ETL Tool: This restructures and transforms Esri formats or other FME-supported formats

340

🤗 Spatial ETL Tool <u>Eile Edit View Insert Readers Transformers Writers Inspection Jools Help</u> 员 Ⅲ ▶ ▶ 🐱 ● | X 🗅 🛍 ♥ (* ▶ ♥ ♥ Q Q 100% ⊖ '-----' ♥ 🕱 🔂 🕏 ♥ ♥ 🕼 🔗 🖶 ₽× Main × wigato WaterBody [GML]
Source Geography Markup Language (GML) ... C Destination: MyTOPO\Hydrography GML source data Coordinate System: "ESRIWKT|Pulkovo_1942... Transformer Parameters Reader Feature Types Writer Feature Types Feature Types
 MyTOPO [GEODATABASE_FILE] Data Flow | ▼ WaterBody M Destination Esri File Geodatabase: H:\PACKT... geodb_oid NAME Coordinate System: "ESRIWKT|Pulkovo_1942... Attribut...ueMapper 🔅 RiverType OBJECTID Output нос gml_id Overwrite Existing Geodatabase: No gml_parent_id HAL Transaction Type: Transactions NAME NAME Template File: < not set> RiverType HAT Simplify Geometry: No gml_cu...operty 🝃 Detect SHAPE_Length Canvas gml_mu...operty 🕻 Contains Measures: No gml_id Advanced HAT Feature Types Navigator Transformers Bookmarks Destination: MyTOPO\Hydrography
 GML source data Log đΧ Transformer Features Written Summary ws User Parameters Translation log 44 WatercourseL 24 ansformer Gallery đΧ ñ Total Features Writter 24 彜 Translation was SUCCESSUL with 5 warning(s) (24 feature(s) output) FME Session Duration: 5.0 seconds. (CPU: 2.0s user, 1.0s system) END - ProcessID: 6960, peak process memory usage: 165948 kB, current Translation was SUCCESSUL Embedded Transformers gallery Recent (10) Q Search Results Q - C Log Help

A **Spatial ETL Tool** is created, edited, and run by the user. A **Spatial ETL Tool** uses a graphic application called **workbench**, as shown in the following screenshot:

In workbench, you can manipulate the geometry and attributes of the datasets using **transformers**. Transformers allow you to restructure and re-project the data source before loading it into the destination data format. There are two types of transformers: geometric and attribute. When you are using a transformer, you have to set all mandatory parameters.

Getting ready

In this recipe, you will explore three data formats: **DWG**, **GML**, and **MIF/MID**. After you finish exploring the interoperability data, you will use the **Spatial ETL Tool** to translate the GML file into a feature class by transforming the data content.


- For more details about the GML format, please refer to http://www. opengeospatial.org/standards/gml
- For more details regarding the MIF/MID data interchange format, please go to http:// www.mapinfo.com/support/Product Documentation and search by MIF/MID
- For more details regarding the FME, please refer to http://www.safe.com/ support/support-resources



How to do it...

Follow these steps to view interoperability data in ArcCatalog:


- 1. Start ArcCatalog. To enable the ArcGIS Data Interoperability extension, go to **Customize | Extensions**, and check **Data Interoperability**.
- 2. In the **Catalog** window, go to the Interoperability\SourceData folder and expand the +DWG, +GML, and +MapInfo folders, as shown in the following screenshot:



- 3. You can directly read a DWG file. Expand the Buildings.dwg file. There are displayed all types of geometry in six CAD feature classes. Navigate to **Buildings.DWG | Polyline** to see the features in the **Preview** pane. Switch **Preview** from the **Geography** mode to the **Table** mode. Explore the attribute fields and note the layers stored in **Layer** field. This field will help us to extract the features based on the dwg layers.
- 4. Let's explore the GML format. Expand the WaterBody.gml interoperability feature class. Use the **Identify** tool to examine the attributes.

To extend the functionality of the direct-read data formats, you can create your own link to data source (interoperability connection) through the Interoperability Connections folder in **Catalog Tree**.

5. In the **Catalog Tree** window, go to Interoperability Connections, and double-click on the **Add Interoperability Connection** tool, as shown in the following screenshots:




- 6. To specify **Format**, click on **Browse the gallery** to open the **FME Reader Gallery** window. Search for MapInfo, and double-click on MapInfo MIF/MID to select the format and exit from the reader gallery.
- Set Dataset by navigating to Interoperability\SourceData\+MapInfo\ Road.mif. Click on OK. The MIF format is directly read by ArcGIS. Expand Connection (1) - Road MIF.fdl to display the feature classes. Here again are listed all types of geometry in five interoperability feature classes.
- 8. Select the Road Polygon feature class and select the **Preview** pane. All features will be indexed and displayed. As shown in the previous screenshot, press the *F5* key to remove all empty feature classes.
- 9. Repeat the steps 5 to 8 to create an interoperability connection for the RoadL MIF/ MID dataset.

Continue to follow the steps to import the GML file into the WatercourseL feature class from MyTOPO.gdb geodatabase created in the *Importing data from the XML format* recipe using the Spatial ETL tool.

- In the ArcToolbox window, right-click on ArcToolbox, select Add Toolbox, and click on the New Toolbox tool. Click on Open. Rename the newly created toolbox as MyInteroperability.
- 11. Right-click on MyInteroperability and navigate to New | Spatial ETL Tool.


12. In the wizard window, define your source format as **GML (Geography Markup Language)**. Click on **Next**. Browse to the SourceData\+GML folder and select the WaterBody.gml file, as shown in the following screenshots:



13. Go to the next panel and define **Destination Format**: Esri Geodatabase (File Geodb ArcObjects). Go to the next two panels, accept the default parameters, select **Static Schema**, and click on **Finish** to create the translation workspace. The workbench has opened.

Firstly, you will add a new writer to the workspace:

- 14. Navigate to Writers | Import Feature Types, and for Dataset, navigate to Interoperability\MyResults\MyTOPO.gdb. Click on OK. In the Select Feature Types window, uncheck Select all. Check only WatercourseL and click on OK.
- 15. Erase the Waterbody writer, and drag a connection from the yellow arrow of the WaterBody reader to the red arrow of the WatercourseL writer, as shown in the following screenshot:



344

In the next step, you will set the destination parameter for Writer:

16. In the Navigator window, double-click on Destination Esri File Geodatabase of <notset>[GEODABASE_FILE], and navigate to MyResults\MyTOPO.gdb. Click on OK.

In the next step, you will set the properties for **Reader**:

17. In workbench canvas, double-click on WaterBody, and select the **User Attributes** tab. Uncheck all attribute fields except NAME and RiverType. This option will extract from the GML file only those two fields. Select the **Format Attributes** tab and uncheck gml id. You should have all format attributes unchecked. Click on **OK**.

In the next step, you will set the properties for Writer:

18. Double-click on WatercourseL and select the **Format Parameters** tab. Select **Yes** for **Truncate Table First** and type Hydrography for **Feature Dataset**, as shown in the following screenshot:

Reature Type Properties	×
General 🔶 User Att	ributes 🔶 Format Attributes 🔅 Format Parameters
Drop Table First:	No ·
Truncate Table First:	Yes 🔻
Update Key Fields:	No items selected.
Object ID Field:	OBJECTID 💌
Object ID Alias:	OBJECTID 🗨
Shape Field:	SHAPE
Shape Alias:	SHAPE
Configuration Keyword:	DEFAULTS
Feature Dataset:	Hydrography
Grid 1:	
Ava Num of Pointer	· · ·
Help Apply to	OK Cancel


19. Select the **User Attributes** tab. Select the **Name** field and move above the **HAT** field with the **Moves the current row up** arrow. This will avoid overlapping links between features in canvas. For the **HAT** field, select the **Type**: subtype. Click on the **Edit** button and define the subtype code, as shown in the following screenshots:

General 🔶 User Attributes	Format Attributes Format	at Parameters	Enter in the list of subtypes below:
Name	Туре	Width Precision	Code
geodb_oid	integer		0
OBJECTID	integer		1
► HOC	integer		2
► HAL	integer		
NAME	char	255	3
► HAT	subtype	Edit	4
SHAPE_Length	double		
Þ.	double		
+ - • • • •	Q, Filte	r	+

20. Click on OK to close all dialog windows.

It's time to perform a data content transformation using an attribute transformer:


21. In the **workbench canvas**, select the connection between **Reader** and **Writer**. Type attri text, select **AttributeValueMapper** to quickly access the transformers gallery, and insert it into the workspace, as shown in the following screenshot:



22. Double-click on the **AttributeValueMapper** transformer to open the **Parameters** dialog. For **Source Attribute**, select the RiverType field. For **Destination Attribute**, type HAT, which classifies the water features.



23. For Source Value, navigate to Import | Source Value to import the values from the RiverType field. Select the WaterBody GML file and click on Next twice. In the Select Attributes for "Source Value" panel, select the RiverType field, and click on Next and Import, as shown in the following screenshots:




24. For the **Destination Value**, type the corresponding code, as shown in the following screenshot:

AttributeValueMapper Parameters								
Transformer								
Transformer Name: Attribu	Transformer Name: AttributeValueMapper							
Attribute Selection								
Source Attribute: 🧔 Riv	Source Attribute:							
Destination Attribute: HAT								
Default Value:	💌							
Mapping Parameters								
Mapping Direction: Forwar	rd (Source To Destination)							
Value Map								
Source Value	Destination Value							
k Canalized stream	<u>k</u> 4							
k Creek	k 3							
k River	<u>k</u> 1							
k Stream	<u>k</u> 2							
+ - * * * *	Import 🔻							
Help	OK Cancel							



Working with Data Interoperability



25. Click on **OK**. In the workbench canvas, create the connection between the **Reader** and **Writer** fields, as shown in the following screenshot:

- 26. Let's add some annotations. Right-click on WaterBody and select **Add Annotation**. Explore the results and edit the default text.
- 27. Let's see the setting of the **AttributeValueMapper** transformer. Right-click on the transformer and select **Show Summary Annotation**. Note that the summary annotation cannot be edited and is colored blue to differentiate from the user annotation.
- 28. Let's add some bookmarks as shown in the preceding image. With bookmarks, you can underline different parts of your workspace, and you have easy access to the different parts of your workspace. Right-click on the empty space on the canvas and select **Insert Bookmarks**. The appearance of the default bookmark can be changed: text, color, dimension, and position. Explore the options.
- 29. Go to the File menu and click on Save.
- 30. Run the translation by selecting the **Run** or **Resume Translation** tool. Exit the workspace. You can modify the **Spatial ETL Tool** by right-clicking on the tool and selecting the **Edit** option.
- 31. Inspect the WatercourseL feature class in ArcCatalog. Note that subtype descriptions were updated for the HAT (Classification) field.

You can find the results at ... $\label{eq:solution} The result of the$



How it works...

The datasets explored in ArcCatalog from steps 2 to 9 can be used in ArcMap like any other Esri data. Those datasets are read-only and cannot be edited. Use the **Quick Import** tool to quickly translate the non-Esri formats to a geodatabase. This tool will save the output in a new geodatabase.

At step 10, we started to create the **Spatial ETL Tool** to import a GML file into your existing geodatabase. Before running a tool, be sure that **Coordinate System** for **Reader** and **Writer** are specified.

From steps 14 to 17, we added **Writer** by importing an existing feature class from the M_{y} TOPO geodatabase.

At step 18, we set the **Writer** properties. To keep the schema of the existing feature class table, we set **Drop Table First** to **No**. To make sure that the destination table was empty, we set **Truncate Table First** to **Yes**. We also mentioned that the WatercourseL output will be a feature class in the Hydrography feature dataset.

At step 19, we added the subtype definition for the WatercourseL feature class output.

From steps 21 to 24, we worked with the **AttributeValueMapper** parameter. It sets up value mapping between the RiverType text field (source) and the subtype codes of the feature class (destination). **Source Values** were imported from the WaterBody GML file.

Here are some best practices to create an easy-to-understand workspace:

- Avoiding overlapping links
- Adding annotation comments and bookmarks to the workspace
- Renaming the transformers
- Disabling/enabling the links (by right-clicking on the link)
- ▶ Using the Translation Log tool

Index

Symbols

2-point line 48 3D Analyst 291 3D features creating, from 2D features 292-296

A

Abbreviation Dictionary tool Ending 159 Keyword 159 Translation 159 addresses geocoding 214-221 address locator Composite_ParcelStreet 228 Parcels_PlaceAlias 228 Streets_AlternateName 228 adjacency topology 56 Adobe Illustrator (AI) 197 **Adobe Reader** URL, for downloading 197 using 197 **Advanced Editing toolbar** using 48-55 animation creating 315-320 annotation feature classes feature-linked annotation feature class 164 not feature-linked annotation feature class 164 annotations about 154 creating 164-172

editing 164-172 geodatabase annotation 154 map document annotation 154 using, for contours 173-176 ArcCatalog custom geographic transformations, defining 84-88 ArcGIS Data Interoperability 322 **ArcGIS Online** about 181 URL 204, 208 ArcGIS template data models URL 330 ArcMap about 15, 195 routes, creating 229 routes, editing 229 used, for studying map projections of Europe 74-78 ArcScene desktop application using 292 atlas about 199 creating 199-203

В

BikeLane model feature classes 117 tools 117 bivariate map about 176 creating 176-179 Blank Map 195

С

calibration 231 **Cell Statistics** working with 271-275 coded domain 19 COGO toolbar using 48-55 coincidence topology 56 complex routes working with 237-240 composite relationship 28 connectivity topology 55 Constanta (Black Sea 1975) 301 containment topology 56 contours annotations, using 173-176 masking 173-176 COordinate GeOmetry (COGO) 48 Coordinate Reference System (CRS) 10, 71 courses 48 custom coordinate reference system defining 94-98 resources 98 setting 93 custom coordinate reference system, parameters geodetic datum 93 projection 93 custom geographic transformations defining, in ArcCatalog 84-88 custom symbology creating 135-139 cyan, magenta, yellow and black (CMYK) 135

D

data importing, from XML format 328-332 interpolating 255-260 preparing, for geocoding 210-213 data interoperability about 321, 322 reference link 322 spatial data format 321 spatial data type 321 viewing 342-348 datum 71 Delaunay triangulation 297 density surfaces creating 279-283 Digital Terrain Model (DTM) 300 domains about 19 and subtypes, using 23-27 coded domain 19 creating 19-23 range domain 19 dots per inch (dpi) 197 DWG 341

Ε

elevation 291 ellipsoidal coordinate system 72 Encapsulated PostScript (EPS) 197 Enhanced Compression Wavelet (ECW) file format about 336 URL 336 Enhanced Metafile (EMF) 197 Esc key 319 Esri ArcGIS 7 ESRI GIS Dictionary about 99 URL 8 Esri Production Mapping extension 198 Eurostat **URL 80** events analyzing 240-243 creating 233-237 editing 233-237 Extensible Markup Language (XML) 323 Extract/Transform/Load (ETL) 322

F

feature class about 12 creating 12-15 importing, in Google Earth 327, 328 feature dataset about 10

creating 10, 11 URL 10 feature-linked annotation feature class 165 Feature Manipulation Engine (FME) about 322 reference link 341 features editing, in geodatabase 37-48 file geodatabase about 8 advantages 8 creating 8-10 exporting, to different data formats 322-328 reference link 8 file geodatabase raster datasets 245

G

geocentric coordinate reference system 72 geocoding about 209 addresses 214-221 alternative names, using 222-228 data, preparing 210-213 URL 210 geodatabase about 7 Advanced Editing toolbar, using 48-55 COGO toolbar, using 48-55 domains, creating 19-23 feature class, creating 12-15 feature dataset, creating 10, 11 features, editing 37-48 relationship class, creating 28-36 subtypes, creating 15-18 URL 8 geodatabase annotation feature-linked annotation 154 not feature-linked annotation 154 geodatabase topology creating 55-61 editing 62-69 geodatabase, types file geodatabase 8 multiuser geodatabase 8 personal geodatabase 8

geodetic datum 71 Geodetic Reference System 1980 (GRS80) 72 Geographic Information Systems (GIS) 7 geoid 72 geoprocess 99 geoprocessing operations used, for analyzing data 113-116 geoprocessing tools data extraction 111 overlay 111 proximity 111 using 111-116 georeferencing, raster data 88-92 GeoTIFF about 197 map, exporting to 197-199 URL 197 GML about 341 reference link 341 GOCE **URL 73 Google Earth** about 327 feature class, importing 327, 328 URL, for installing 327 graphic text adding 155-158 gravity-related height 292

Η

height 291 HSV 135 hue 135

INSPIRE Directive 74 interoperability 321 Intervisibility 309-311 Inverse Distance Weighted (IDW) 255

J

Joint Photographic Experts Group (JPEG) 197



Κ

Kernel Density Estimation (KDE) 279 kernel density function using 280 keyframes 315 Keyhole Markup Language (KML) about 327 reference link 327

L

labels creating 154-158 creating, with Maplex Label Engine 160-164 editing 154-158 Lambert Azimuthal Equal Area 78 least-cost path about 283 analyzing 283-288 creating 284-288 Light Detection and Ranging (LiDAR) 300 linear referencing URL 210

Μ

Magnifier using 164 map exporting, in raster format 197 exporting, in vector format 197 exporting, to GeoTIFF 197, 198 exporting, to PDF 197, 198 publishing, on Internet 204-208 Map Algebra about 265 working with 265-271 map document annotation 154 map layout about 182 creating 182-196 **Maplex Label Engine** labels, creating 160-164 map, methods for publishing exported maps 204 layer package (lpk) 204

map package (mpk) 204 tile package (tpk) 204 web maps 204 masking 173-176 Mean Sea Level (MSL) 292 metadata 93 Microsoft typography URL 198 MIF/MID about 341 reference link 341 Model Builder about 116, 254 working with 279 models about 116 creating 116-123 multiuser geodatabase 8

Ν

natural neighbors interpolation method using 309 normal height (H) 292 not feature-linked annotation feature class 164

0

Open Geospatial Consortium URL 322 Ordnance Survey MasterMap URL 322

Ρ

personal geodatabase 8 Portable Document Format (PDF) about 197 map, exporting to 197, 198 PowerPoint 199 profile graph about 311 creating 311-315 projected coordinate reference system 72 projections about 74 Azimuthal 74

Conical 74 Cylindrical 74 proportional symbology using 139-142

Q

Quick Export 340 Quick Import 340

R

range domain 19 raster creating, from terrain dataset 306-309 generalizing 276-279 reclassifying 260-264 raster data georeferencing 88-92 importing 336-340 Red, Green and Blue (RGB) 135 region 276 relationship class about 28 creating 28-36 relationship, types composite 28 simple 28 representation using 145-151 routes creating 228-232 editing 228-232

S

simple relationship 28 spatial adjustment using 106-111 Spatial Analyst about 245 URL 246 Spatial ETL Tool about 340 using 340-349 spatial interpolation 255 spatial joining features using 100-105 Spatial Join tool 100 spherical coordinate system 72 Spline 255, 260 styles about 126 managing 126-129 style set 126 subtypes about 15 and domains, using 23-27 creating 15-18 **Surface Analysis model** Edit mode 254 Tool dialog option 254 surfaces analyzing 246-253 symbol levels using 142-145 symbols modifying 131-135

T

Tagged Image File Format (TIFF) 197 terrain 300 terrain dataset about 300 creating 300-306 raster, creating 306-309 TIN, creating 306-309 terrain surface 300 TIN about 297 creating, from terrain dataset 306-309 **TIN surface** creating 297-300 tools, to represent quantitative data Dot density 139 Graduated colors 139 Graduated symbols 139 Proportional symbols 139 topology about 55 adjacency 56 coincidence 56 connectivity 55

containment 56 reference link 56, 62 transformation process 340 transformers 341 translation, interoperability data feature, using 340 feature type, using 340 reader, using 340 workspace, using 340 writer, using 340 Triangulated Irregular Network. See TIN

V

Value Attribute Table (VAT) 248 vector data characteristics, inspecting 332 importing 332-335 projecting 79-83 VeloGIS 99 VeloGIS.gdb file compacting 105 vertical coordinate reference system 72 Vertical Coordinate Systems 73 VLC 315

W

Windows Media Player 315 workbench 341 workspace best practices 349

X

XML format data, importing from 328-332

Ζ

ZIP code 211 zone 276



PACKT Thank you for buying ArcGIS for Desktop Cookbook

About Packt Publishing

Packt, pronounced 'packed', published its first book, *Mastering phpMyAdmin for Effective MySQL Management*, in April 2004, and subsequently continued to specialize in publishing highly focused books on specific technologies and solutions.

Our books and publications share the experiences of your fellow IT professionals in adapting and customizing today's systems, applications, and frameworks. Our solution-based books give you the knowledge and power to customize the software and technologies you're using to get the job done. Packt books are more specific and less general than the IT books you have seen in the past. Our unique business model allows us to bring you more focused information, giving you more of what you need to know, and less of what you don't.

Packt is a modern yet unique publishing company that focuses on producing quality, cutting-edge books for communities of developers, administrators, and newbies alike. For more information, please visit our website at www.packtpub.com.

Writing for Packt

We welcome all inquiries from people who are interested in authoring. Book proposals should be sent to author@packtpub.com. If your book idea is still at an early stage and you would like to discuss it first before writing a formal book proposal, then please contact us; one of our commissioning editors will get in touch with you.

We're not just looking for published authors; if you have strong technical skills but no writing experience, our experienced editors can help you develop a writing career, or simply get some additional reward for your expertise.






Building Web and Mobile ArcGIS Server Applications with JavaScript

ISBN: 978-1-84969-796-5

Paperback: 274 pages

Master the ArcGIS API for JavaScript, and build exciting, custom web and mobile GIS applications with the ArcGIS Server

- 1. Develop ArcGIS Server applications with JavaScript, both for traditional web browsers as well as the mobile platform.
- 2. Acquire in-demand GIS skills sought by many employers.



Programming ArcGIS 10.1 with Python Cookbook

ISBN: 978-1-84969-444-5


Paperback: 304 pages

Over 75 recipes to help you automate geoprocessing tasks, create solutions, and solve problems for ArcGIS with Python

- 1. Learn how to create geoprocessing scripts with ArcPy.
- 2. Customize and modify ArcGIS with Python.
- 3. Create time-saving tools and scripts for ArcGIS.

Please check www.PacktPub.com for information on our titles






Google Maps JavaScript API Cookbook

ISBN: 978-1-84969-882-5

Paperback: 316 pages

Over 50 recipes to help you create web maps and GIS web applications using the Google Maps JavaScript API

- 1. Add to your website's functionality by utilizing Google Maps' power.
- 2. Full of code examples and screenshots for practical and efficient learning.
- 3. Empowers you to build your own mapping application from the ground up.



Administering ArcGIS for Server

ISBN: 978-1-78217-736-4

Paperback: 246 pages

Installing and configuring ArcGIS for Server to publish, optimize, and secure GIS services

- 1. Configure ArcGIS for Server to achieve maximum performance and response time.
- 2. Understand the product mechanics to build up good troubleshooting skills.
- 3. Filled with practical exercises, examples, and code snippets to help facilitate your learning.

Please check www.PacktPub.com for information on our titles